



# CalibrationLibrary – Application Programming Interface

CalibrationLibrary **V1.4.0**

SCANLAB GmbH  
Siemensstr. 2a  
82178 Puchheim  
Germany

Tel.+49 (89) 800 746-0  
Fax+49 (89) 800 746-199

[info@scanlab.de](mailto:info@scanlab.de)  
[www.scanlab.de](http://www.scanlab.de)

© SCANLAB GmbH

SCANLAB GmbH reserves the right to change the information in this document without notice.

No part of this document may be processed, reproduced or distributed in any form (photocopy, print, microfilm or by any other means), electronic or mechanical, for any purpose without the written permission of SCANLAB GmbH.

All mentioned trademarks are hereby acknowledged as properties of their respective owners.



## Contents

<b>1</b>	<b>About this Manual .....</b>	<b>5</b>
1.1	Related Documents .....	5
1.2	Manufacturer .....	5
1.3	Intended Use.....	6
1.4	Safety.....	7
1.5	Prerequisites.....	7
1.6	Glossary .....	8
<b>2</b>	<b>Software Development with the CalibrationLibrary DLL .....</b>	<b>10</b>
2.1	Installation .....	10
<b>3</b>	<b>Functions Available in the API .....</b>	<b>11</b>
3.1	Functional Overview.....	11
3.1.1	Administration Functions .....	11
3.1.2	Correction table Evaluation Functions.....	12
3.1.3	Correction table Parameter Access Functions .....	12
3.1.4	Calibration Optimization Functions.....	13
3.2	Function Reference .....	14
3.2.1	General Structure of the Reference Tables .....	14
3.2.2	Data Types of the CalibrationLibrary DLL Functions .....	15
3.2.3	Reference Tables .....	16
	slcl_activate.....	16
	slcl_convert_ctb_to_ct5.....	16
	slcl_delete_correction_table_handle.....	17
	slcl_disable_logging .....	17
	slcl_do_abc_calibration .....	18
	slcl_do_beam_tilt_calibration.....	19
	slcl_do_beam_tilt_calibration_measurement_data.....	20
	slcl_do_cone_calibration .....	21
	slcl_do_cylinder_calibration .....	22
	slcl_do_focus_calibration .....	23
	slcl_do_freeform_pointcloud_calibration .....	24
	slcl_do_plane_calibration .....	25
	slcl_do_scale_calibration .....	26
	slcl_do_stretch_calibration .....	27
	slcl_enable_logging.....	28
	slcl_get_current_abc_coeffs .....	28
	slcl_get_current_calibration_factor .....	29
	slcl_get_current_stretch_factors.....	29
	slcl_get_lib_version .....	30
	slcl_get_z_distance.....	31
	slcl_inverse_transform_points_2d .....	32
	slcl_inverse_transform_points_2d_io.....	33
	slcl_inverse_transform_points_3d .....	34
	slcl_inverse_transform_points_3d_fixed_z.....	35
	slcl_inverse_transform_points_3d_fixed_z_io.....	36
	slcl_inverse_transform_points_3d_io.....	37
	slcl_inverse_transform_points_3d_io_with_trafos .....	38
	slcl_inverse_transform_points_3d_with_trafos.....	39

slcl_load_correction_table .....	40
slcl_save_correction_table .....	41
slcl_set_abc_manually .....	41
slcl_set_ct5_parameters_manually .....	42
slcl_set_stretch_factors_manually .....	42
slcl_transform_points_2d .....	43
slcl_transform_points_2d_io .....	44
slcl_transform_points_3d .....	45
slcl_transform_points_3d_io .....	46
slcl_xy_calibration_bit_targets .....	47
slcl_xy_calibration_bit_targets_callback .....	48
slcl_xy_calibration_mm_targets .....	49
slcl_xy_calibration_mm_targets_callback .....	50
<b>4 Structures struct .....</b>	<b>51</b>
slcl_abc_pol_coefficients .....	51
slcl_additional_transformations .....	52
slcl_ct5_table_readme_parameters .....	54
slcl_stretch_factors .....	55
slcl_xy_calibration_interpolation_results .....	56
slcl_xy_calibration_settings .....	58
VersionInfo .....	60
<b>5 Enumerated Types enum .....</b>	<b>61</b>
slcl_error_codes .....	62
slcl_xy_calibration_options .....	64
<b>6 Example.cpp .....</b>	<b>66</b>
<b>7 Change Index .....</b>	<b>72</b>

## 1 About this Manual

This manual describes the SCANLAB  
CalibrationLibrary DLL **V1.4.0**.

### Notice!

Carefully read the document "Software License Agreement" before installing and using CalibrationLibrary. This agreement defines matters such as terms of usage, warranty information and liability disclaimers. If you have questions, simply contact SCANLAB.



### Caution!

Read and observe all safety instructions in this manual!

SCANLAB accepts no liability for damages or consequential losses resulting from non-observance of this manual, in particular the safety instructions contained herein.

### 1.1 Related Documents

- RTC4 Manual
- RTC5 Manual
- RTC6 Manual
- Calibrating a 3-Axis Laser Scan System

### 1.2 Manufacturer

SCANLAB GmbH  
Siemensstr. 2a  
82178 Puchheim  
Germany  
Tel. +49 (89) 800 746-0  
Fax +49 (89) 800 746-199  
[info@scanlab.de](mailto:info@scanlab.de)  
[www.scanlab.de](http://www.scanlab.de)



### 1.3 Intended Use

CalibrationLibrary DLL (32-bit version and 64-bit version) is part of Calibration Library software package #148051.

For developing user programs under MS Windows it provides a programming interface (API) in the form of functions. These allow:

- Loading, handling, and creating **Correction files** in SCANLAB format
- Offline transformation of bit coordinates using **Correction files**
- Simple access functions to set and retrieve certain parameters from **Correction tables**
- Improvement of **Correction files** based on user measurements

CalibrationLibrary DLL is a program library with a collection of functions. These are intended for 2D calibration and 3D calibration of SCANLAB scan systems. The functions can be implemented in existing program code and thus support the development of customized *automated calibration routines* for scan systems.

By calling functions in a dedicated manner, a SCANLAB standard correction file (\*.ct5 or \*.ctb) loaded at the beginning can be converted step by step into a new, system-specific correction file. In this way, higher accuracies can be achieved with the scan system than with the initial correction file.

For the choice of the order of these functions, see the document **Calibrating a 3-Axis Laser Scan System**.

Furthermore, CalibrationLibrary DLL offers the following possibilities:

- Certain parameters of the loaded **Correction file** can be
  - queried
  - changed
- Offline transformations of bit coordinates
- Calculating (forward) transformations and inverse transformations that would otherwise (after corresponding RTC command calls) only take place on the RTC board itself

For access to all functionalities of CalibrationLibrary DLL are available:

- the "normal" C-API
- C# wrapper
- Python wrapper



## 1.4 Safety

### Notice!

Carefully read the document "Software License Agreement" before installing and using CalibrationLibrary. This agreement defines matters such as terms of usage, warranty information and liability disclaimers. If you have questions, simply contact SCANLAB.



### Caution!

Check your generated correction files before using them in production, for example, whether test markers have the expected quality.

## 1.5 Prerequisites

Precondition for the usage of the CalibrationLibrary DLL:

- Windows 10 PC

## 1.6 Glossary

2D-Correction file	Correction file with 2D-Correction table.
2D-Correction table	Correction table with 2D data. Corresponding to the file extension: <ul style="list-style-type: none"> <li>2D-ct5-Correction table</li> <li>2D-ctb-Correction table</li> </ul>
3D-Correction file	Correction file with 3D-Correction table.
3D-Correction table	Correction table with 3D data. Corresponding to the file extension: <ul style="list-style-type: none"> <li>3D-ct5-Correction table</li> <li>3D-ctb-Correction table</li> </ul>
ABC Calibration	The term refers to: <b>slcl_do_abc_calibration</b>
API	Abbreviation of Application Programming Interface. Program part (here: of the CalibrationLibrary DLL) which is available for other programs for connecting to the system (here: functions of the CalibrationLibrary DLL). See <b>Chapter 3 "Functions Available in the API", page 11.</b>
Beam Tilt Calibration	The term refers to: <b>slcl_do_beam_tilt_calibration</b>
Callback event	One of several CalibrationLibrary DLL-internal events. See also <b>Callback function.</b>
Callback function	Designates a user-supplied function that is to be executed when a certain "Callback event" occurs.  A "Callback function" is registered to the CalibrationLibrary DLL via a Function for registering "Callback event". <ul style="list-style-type: none"> <li><b>slcl_xy_calibration_bit_targets_callback</b></li> <li><b>slcl_xy_calibration_mm_targets_callback</b></li> </ul> Therefore, it must comply to a dictated function signature: <ul style="list-style-type: none"> <li><code>void ( const char*, int32_t, void* )</code></li> </ul>
Cone Calibration	The term refers to: <b>slcl_do_cone_calibration</b>
Correction file	File in SCANLAB format *.ctb or *.ct5. Contains the <b>Correction table(s)</b> . For further information <b>Calibrating a 3-Axis Laser Scan System.</b>
Correction table	Relevant information inside the <b>Correction file.</b>
<b>Correction table</b> instance	Instance of a certain <b>Correction table</b> . Is a <b>Correction table</b> object which is created when <b>slcl_load_correction_table</b> is called. Every <b>Correction table instance</b> is represented by exactly one <b>Handle</b> and can be addressed by it.
ct5-Correction file	File in SCANLAB format *.ct5.
ct5-Correction table	Correction table of the ct5-Correction file: <ul style="list-style-type: none"> <li>3D-ct5-Correction table</li> <li>2D-ct5-Correction table</li> </ul>



ctb-Correction file	<ul style="list-style-type: none"> <li>File in SCANLAB format *.ctb.</li> </ul>
ctb-Correction table	<p>Correction table of the ctb-Correction file:</p> <p>2D-ctb-Correction table</p> <p>3D-ctb-Correction table</p>
Cylinder Calibration	<p>The term refers to:</p> <p><b>slcl_do_cylinder_calibration</b></p>
Focus Calibration	<p>The term refers to:</p> <p><b>slcl_do_focus_calibration</b></p>
Handle	<p>Computer programming term: abstract reference to a resource. In this manual, this term refers to a certain <b>Correction table instance</b>. Its <b>Handle</b> value is assigned by <b>slcl_load_correction_table</b>. With the (most) CalibrationLibrary functions, the <b>Handle</b> value of the desired target-<b>Correction table instance</b> must be specified.</p>
NULL	<p>Means on the one hand the number 0, on the other hand a pointer with the value 0.</p>
Plane Calibration	<p>The term refers to:</p> <p><b>slcl_do_plane_calibration</b></p>
Readme file	<p>Text file supplied by SCANLAB together with the <b>Correction file</b>:</p> <ul style="list-style-type: none"> <li>Exactly the same name as the <b>Correction file</b></li> <li>for <b>ctb-Correction files</b> "_ReadMe" is appended</li> <li>For <b>ct5-Correction files</b> "_ct5_ReadMe" is appended</li> <li>File extension is *.txt</li> </ul> <p>For more information, see <b>Calibrating a 3-Axis Laser Scan System</b>.</p>
Scale Calibration	<p>The term refers to:</p> <p><b>slcl_do_scale_calibration</b></p>
Stretch Calibration	<p>The term refers to:</p> <p><b>slcl_do_stretch_calibration</b></p>
User	<p>Designates a person (= "system programmer") who develops user programs using the CalibrationLibrary software package.</p> <p>Not meant is the "user or operator of a CalibrationLibrary system".</p>
XY Calibration	<p>The term refers to:</p> <p><b>slcl_xy_calibration_bit_targets</b> or <b>slcl_xy_calibration_bit_targets_callback</b> or <b>slcl_xy_calibration_mm_targets</b> or <b>slcl_xy_calibration_mm_targets_callback</b></p>



## 2 Software Development with the CalibrationLibrary DLL

The first step when using the CalibrationLibrary is to activate its functions by calling `slcl_activate` with the correct password. If `slcl_activate` has not been successfully called, none of the other CalibrationLibrary functions can be used!

### Notice!

The password for `slcl_activate` can be obtained from SCANLAB or is included in the Calibration Library software package.

To interface with the internal functionality of the CalibrationLibrary you need a reference pointer called **Handle**. Each **Handle** represents an **Correction table instance**. The **Handle** is generated by calling `slcl_load_correction_table` and needs to be handed over to the **API** with every function call. You can generate as many **Handles** as needed. These can be deleted again selectively by `slcl_delete_correction_table_handle`. See also Chapter 6 "Example.cpp", page 66.

### 2.1 Installation

There are different ways to integrate the CalibrationLibrary DLL into your user program. The following is an example of how to integrate CalibrationLibrary DLL into a 32-bit Microsoft Visual Studio project.

- (1) Copy `CalibrationLibrary32.dll` to your Binary directory.
- (2) Add the `CalibrationLibrary32.lib` as a dependency to your project.
- (3) Place `CalibrationLibrary.h` in your Include directory.
- (4) Include the `CalibrationLibrary.h` in your project by `#include "CalibrationLibrary.h"`.
- (5) You can now use the CalibrationLibrary DLL functions. See also Chapter 6 "Example.cpp", page 66.

## 3 Functions Available in the API

### 3.1 Functional Overview

In this chapter:

- [Administration Functions, page 11](#)
- [Correction table Evaluation Functions, page 12](#)
- [Correction table Parameter Access Functions, page 12](#)
- [Calibration Optimization Functions, page 13](#)

#### 3.1.1 Administration Functions

Functions for generating, deleting and saving **Handles** to interface with CalibrationLibrary.

- [slcl\\_activate, Page 16](#)
- [slcl\\_delete\\_correction\\_table\\_handle, Page 17](#)
- [slcl\\_disable\\_logging, Page 17](#)
- [slcl\\_enable\\_logging, Page 28](#)
- [slcl\\_get\\_lib\\_version, Page 30](#)
- [slcl\\_load\\_correction\\_table, Page 40](#)
- [slcl\\_save\\_correction\\_table, Page 41](#)
- [slcl\\_set\\_ct5\\_parameters\\_manually, Page 42](#)

### 3.1.2 **Correction table** Evaluation Functions

Functions for using a **Correction table** to transform working field bit values into control bit values and vice versa.

**Correction table Evaluation Functions** can be used to evaluate a **Correction table**. With the various transform functions, working field bit values can be transformed into control bit values while the inverse transform functions convert control bit values into working field bit values.

#### Notes

- Inverse transformations are only available for **ct5-Correction tables**:
  - All calculations can be done with just a single **Correction file**
  - An RTC board is not required
- **slcl\_get\_z\_distance**
- **slcl\_inverse\_transform\_points\_2d**, Page 32
- **slcl\_inverse\_transform\_points\_2d\_io**, Page 33
- **slcl\_inverse\_transform\_points\_3d**, Page 34
- **slcl\_inverse\_transform\_points\_3d\_fixed\_z**, Page 35
- **slcl\_inverse\_transform\_points\_3d\_fixed\_z\_io**, Page 36
- **slcl\_inverse\_transform\_points\_3d\_io**, Page 37
- **slcl\_inverse\_transform\_points\_3d\_io\_with\_trafos**, Page 38
- **slcl\_inverse\_transform\_points\_3d\_with\_trafos**, Page 39
- **slcl\_transform\_points\_2d**, Page 43
- **slcl\_transform\_points\_2d\_io**, Page 44
- **slcl\_transform\_points\_3d**, Page 45
- **slcl\_transform\_points\_3d\_io**, Page 46

### 3.1.3 **Correction table** Parameter Access Functions

Functions for retrieving or setting certain parameters for a given **Correction table**.

**Correction table Parameter Access Functions** may be used to retrieve certain parameters from a **Correction table** and to make simple alterations to other **Correction tables**. If a parameter is set by **Correction table Parameter Access Functions**, no calculations are performed and the parameter is simply set to the new value.

- **slcl\_get\_current\_abc\_coeffs**, Page 28
- **slcl\_get\_current\_calibration\_factor**, Page 29
- **slcl\_get\_current\_stretch\_factors**, Page 29
- **slcl\_set\_abc\_manually**, Page 41
- **slcl\_set\_stretch\_factors\_manually**, Page 42

### 3.1.4 Calibration Optimization Functions

Functions for improving a given **Correction table** based on user input.

**Calibration Optimization Functions** perform internal calculations to improve the **Correction file** based on the given input.

When improving **Correction file** it is critical to adhere to a logical order. Otherwise, one method of improvement may invalidate another.

Any of these steps may be skipped, but the sequence must never be altered:

- (1) Converting **ctb-Correction files** to **ct5-Correction files**
- (2) **Plane Calibration** OR **Cylinder Calibration** OR **Cone Calibration**
- (3) **Scale Calibration** OR **Cone Calibration**
- (4) **Beam Tilt Calibration**
- (5) **XY Calibration**
- (6) **Focus Calibration**
- (7) **ABC Calibration** AND/OR **Stretch Calibration** - any or all may be done in any order
  - **slcl\_convert\_ctb\_to\_ct5**, Page 16
  - **slcl\_xy\_calibration\_bit\_targets**, Page 47
  - **slcl\_xy\_calibration\_bit\_targets\_callback**, Page 48
  - **slcl\_xy\_calibration\_mm\_targets**, Page 49
  - **slcl\_xy\_calibration\_mm\_targets\_callback**, Page 50
  - **slcl\_do\_abc\_calibration**, Page 18
  - **slcl\_do\_beam\_tilt\_calibration**, Page 19
  - **slcl\_do\_beam\_tilt\_calibration\_measurement\_data**, Page 20
  - **slcl\_do\_cone\_calibration**, Page 21
  - **slcl\_do\_cylinder\_calibration**, Page 22
  - **slcl\_do\_focus\_calibration**, Page 23
  - **slcl\_do\_freeform\_pointcloud\_calibration**, Page 24
  - **slcl\_do\_plane\_calibration**, Page 25
  - **slcl\_do\_scale\_calibration**, Page 26
  - **slcl\_do\_stretch\_calibration**, Page 27

## 3.2 Function Reference

In this chapter:

- [Chapter 3.2.1 "General Structure of the Reference Tables", page 14](#)
- [Chapter 3.2.2 "Data Types of the CalibrationLibrary DLL Functions", page 15](#)
- [Chapter 3.2.3 "Reference Tables", page 16](#)

### 3.2.1 General Structure of the Reference Tables

Name of the function	<b>prefix_name</b> CalibrationLibrary functions have the prefix "slcl_".
Purpose	Short description describing the purpose of the function.
Function signature	<pre>datatype prefix_name(datatype A, datatype* B, datatype C)   &gt; Line Argument(s) C   &gt; Line Argument(s) B<sup>(a)</sup>   &gt; Line Argument(s) A   &gt; Lines Name of the function, Purpose   &gt; Line Return value</pre> <p>Example: <code>uint32_t slcl_load_correction_table( size_t* Handle, const char* CorrFilename, const char* ReadMeFilename )</code></p>
Argument(s)	A            Data type. Short text.
	B            Data type. Short text.
	C            Data type. Short text.
Return value	Reference to a description of the return value, for example, "See <a href="#">Standard return values of CalibrationLibrary functions, page 62</a> ".
Comment(s)	<ul style="list-style-type: none"> <li>• Additional information on this and similar functions.</li> <li>• References to other chapters and publications.</li> </ul>
Code example	<a href="#">Example.cpp</a>
Version info	States the CalibrationLibrary DLL version in which the function has been published for the first time and, if applicable, further information on changes.
References	Links to related functions: <b>prefix_name_2</b>

(a) 'datatype\*' (address operator) indicates a pointer.

### 3.2.2 Data Types of the CalibrationLibrary DLL Functions

C programming language	Data format
char	A presentable character of 1 byte = 8 bit.
char*	Pointer to a \0-terminated ANSI string, 1 byte per char. 4 Byte for Win32 executables. 8 Byte for Win64 executables. Synonym: char array, C-string.
double	64-bit IEEE floating point format. See <a href="https://de.wikipedia.org/wiki/IEEE_754">https://de.wikipedia.org/wiki/IEEE_754</a> .
double*	Pointer to a double value. double* can be an array also.
int32_t	Signed 32-bit value: $[-2^{31} \dots + (2^{31}-1)]$ .
int32_t*	Pointer to a signed 32-bit value: $[-2^{31} \dots + (2^{31}-1)]$ .
size_t	As defined in <code>stddef.h</code> . In general, <code>uint32_t</code> for Win32 Executables.
size_t*	Pointer to a <code>size_t</code> value.
uint16_t	Unsigned 16-bit value: $[0 \dots + (2^{16}-1)]$ . Synonym: unsigned short.
uint32_t	Unsigned 32-bit value: $[0 \dots + (2^{32}-1)]$ . Synonym: unsigned int.
uint32_t*	Pointer to a unsigned 32-bit value: $[0 \dots + (2^{32}-1)]$ .
uint64_t	Unsigned 64-bit value: $[0 \dots + (2^{64}-1)]$ . Synonym: unsigned long long.
uint64_t*	Pointer to a unsigned 64-bit value: $[0 \dots + (2^{64}-1)]$ .

#### Notes

- **\*\***  
means pointer to a pointer, for example, with **slcl\_load\_correction\_table**.
- **const**  
(for example, with `const uint64_t Password`) means that the value that follows is not changeable. That is, after the function call the value is the same as before the function call (unlike `size_t*`). `const` is used to differentiate these values from returned parameter values.
- **void**  
means that the function does not deliver a return value.
- **void\***  
means a pointer to a generic data type.

### 3.2.3 Reference Tables

The sequence of the reference tables in this chapter is alphabetically.

Name of the function	<b>slcl_activate</b>
Purpose	Category: <b>Administration Functions</b> . Activates CalibrationLibrary by password.
Function signature	<code>uint32_t slcl_activate( uint64_t Password )</code>
Argument(s)	Password      64-bit value for activation of CalibrationLibrary.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>The first step when using the CalibrationLibrary is to activate its functions by calling <b>slcl_activate</b> with the correct Password successfully. If <b>slcl_activate</b> has not been successfully called, none of the other functions can be used!</li> </ul>
Code example	See <b>Example.cpp</b> .
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	See <b>Example.cpp</b> .

Name of the function	<b>slcl_convert_ctb_to_ct5</b>
Purpose	Category: <b>Calibration Optimization Functions</b> . Converts an existing <b>ctb-Correction file</b> into a fully valid <b>ct5-Correction file</b> .
Function signature	<code>uint32_t slcl_convert_ctb_to_ct5( size_t CtbHandle, size_t* Ct5HandleNew, const char* NewCt5Filename )</code>
Argument(s)	CtbHandle      Handle of the <b>ctb-Correction table</b> that is to be converted.
	Ct5HandleNew      Memory address of the newly constructed <b>ct5-Correction table</b> that is generated by <b>slcl_convert_ctb_to_ct5</b> .
	NewCt5Filename      Name of the <b>ct5-Correction file</b> that the resulting <b>ct5-Correction table</b> shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li><b>slcl_convert_ctb_to_ct5</b> requires parameters from the <b>Readme file</b> of the <b>ctb-Correction file</b>!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–



Name of the function	<code>slcl_delete_correction_table_handle</code>
Purpose	Category: <b>Administration Functions</b> . Release a specific <b>Correction table</b> object.
Function signature	<code>uint32_t slcl_delete_correction_table_handle( size_t Handle )</code>
Argument(s)	Handle <b>Handle</b> to be released.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	• –
Code example	See <b>Example.cpp</b> .
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	<code>slcl_disable_logging</code>
Purpose	Category: <b>Administration Functions</b> . Disables CalibrationLibrary logging.
Function signature	<code>uint32_t slcl_disable_logging(void)</code>
Argument(s)	–
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	• Logging is by default enabled after activation.
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	<b><code>slcl_enable_logging</code></b>

Name of the function	slcl_do_abc_calibration
Purpose	Category: <b>Calibration Optimization Functions</b> . Calculates the ABC coefficients for the selected table for a given set of measurements for the focal length and the Z-control bit.
Function signature	<code>uint32_t slcl_do_abc_calibration( size_t Handle, uint16_t NPoints, const int32_t* FocalLengthsBit, const int32_t* ZControlBit, const char* NewFilename, slcl_abc_pol_coefficients* CalculatedCoeffs )</code>
Argument(s)	Handle <b>Handle</b> for the <b>Correction table</b> to be used. Its ABC coefficients will be modified by the function.
	NPoints      Number of measured points.
	FocalLengthsBit      Pointer to an array of dimension NPoints. This array must contain the measured focal lengths: <ul style="list-style-type: none"> <li>• As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>• As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	ZControlBit      Pointer to an array of dimension NPoints. This array must contain the measured z control values: <ul style="list-style-type: none"> <li>• As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>• As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
	CalculatedCoeffs      Pointer to the struct <code>slcl_abc_pol_coefficients</code> containing the new coefficients.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	• –
Code example	See <b>Example.cpp</b> .
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	<b>slcl_do_beam_tilt_calibration</b>
Purpose	Category: <b>Calibration Optimization Functions</b> . Recalculates the <b>Correction table</b> using offset values measured for galvanometer scanner angles of 0.
Function signature	<code>uint32_t slcl_do_beam_tilt_calibration( size_t Handle, double OffsetXMM, double OffsetYMM, const char* NewFilename )</code>
Argument(s)	Handle <b>Handle of a 3D-Correction table</b> that is to be improved. Must not be a <b>2D-Correction table</b> .
	OffsetXMM      Measured x offset value for galvanometer scanner angle of 0. In mm.
	OffsetYMM      Measured y offset value for galvanometer scanner angle of 0. In mm.
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>• <b>slcl_do_beam_tilt_calibration</b> parameters from the <b>Readme file</b>!</li> <li>• If you do not want to calculate the offset values yourself, use <b>slcl_do_beam_tilt_calibration_measurement_data</b>.</li> <li>• <b>slcl_do_beam_tilt_calibration</b> requires the previous calculation of <code>OffsetXMM</code> and <code>OffsetYMM</code>. Alternatively, you can use <b>slcl_do_beam_tilt_calibration_measurement_data</b>, which additionally takes over the calculation of the offset values.</li> </ul>
Code example	See <b>Example.cpp</b> .
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	<b>slcl_do_beam_tilt_calibration_measurement_data</b>

Name of the function	slcl_do_beam_tilt_calibration_measurement_data
Purpose	<p>Category: <b>Calibration Optimization Functions</b>.</p> <p>Recalculates the <b>Correction table</b> using the measured difference values (First, calculates the offset values for galvanometer scanner angle of 0 (= <b>OffsetXMM</b>, <b>OffsetYMM</b>) from <b>DeltaXMM</b>, <b>DeltaYMM</b>, <b>HeightMM</b>. Then calls <b>slcl_do_beam_tilt_calibration</b>).</p>
Function signature	<pre>uint32_t slcl_do_beam_tilt_calibration_measurement_data( size_t Handle, double DeltaXMM, double DeltaYMM, double HeightMM, const char* NewFilename )</pre>
Argument(s)	<p><b>Handle</b>                      <b>Handle</b> of a <b>3D-Correction table</b> that is to be improved. Must not be a <b>2D-Correction table</b>.</p>
	<p><b>DeltaXMM</b>                      Measured difference in x direction. In mm.</p>
	<p><b>DeltaYMM</b>                      Measured difference in y direction. In mm.</p>
	<p><b>HeightMM</b>                      Distance between the 2 measuring planes in z direction. In mm.</p>
	<p><b>NewFilename</b>                      Name of the file that the result shall be saved to. If NULL, the result is not saved.</p>
Return value	See <b>Standard return values of CalibrationLibrary functions</b> , page 62.
Comment(s)	<ul style="list-style-type: none"> <li><b>slcl_do_beam_tilt_calibration_measurement_data</b> parameters from the <b>Readme file</b>!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.4.0.
References	<b>slcl_do_beam_tilt_calibration</b>

Name of the function	slcl_do_cone_calibration
Purpose	Category: <b>Calibration Optimization Functions</b> . Recalculates a <b>3D-Correction file</b> for a user-defined conic target surface that can be shifted, tilted, and rotated.
Function signature	<code>uint32_t slcl_do_cone_calibration( size_t Handle, const double* ReferencePointMM, const double* ConeDirection, const double ConeRadiusAtOriginMM, const double ConeInclinationAngleRad, const char* NewFilename )</code>
Argument(s)	Handle <b>Handle</b> of the <b>Correction table</b> that is to be changed. Must be 3d.
	ReferencePointMM      Pointer to an array of dimension 3 containing a reference point on the cone.
	ConeDirection      Pointer to an array of dimension 3 containing the direction of the cone axis.
	ConeRadiusAtOriginMM      Radius of the cone at the reference point. In mm.
	ConeInclinationAngleRad      Inclination angle of the cone. In rad. Must be between $\pm\pi/3$ . Must not be <b>NULL</b> .
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>The target surface must be provided as a reference point, a direction vector, the radius at the reference point and the inclination angle of the cone. The reference point is a point on the lateral surface of the cone and represents the new coordinate origin of the target surface. In the cross-section of the cone that is perpendicular to the direction of the cone it is the point with the largest z coordinate. The given direction is the direction of the cone axis, which will represent the x coordinate in the new coordinate system. The new y coordinate is the angular offset from the surface line going through the reference point multiplied by the radius of the cone at the reference point. This means that the same y coordinate describes a shorter distance at a more narrow part of the cone and a larger distance at a wider part of the cone. The inclination angle is provided in radians and must positive if the cone widens for larger values of x, and negative if it becomes more narrow.</li> <li>The new file should not be used for points outside the provided target surface.</li> <li><b>slcl_do_cone_calibration</b> requires parameters from the <b>Readme file</b>!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_do_cylinder_calibration
Purpose	Category: <b>Calibration Optimization Functions</b> . Recalculates a <b>3D-Correction file</b> for a user-defined cylindrical target surface that can be shifted, tilted, and rotated.
Function signature	<code>uint32_t slcl_do_cylinder_calibration( size_t Handle, const double* ReferencePointMM, const double* CylinderDirection, const double CylinderRadiusMM, const char* NewFilename )</code>
Argument(s)	Handle <b>Handle of the 3D-Correction table</b> that is to be changed. Must not be a <b>2D-Correction table</b> .
	ReferencePointMM      Pointer to an array of dimension 3 containing a reference point on the cylinder.
	CylinderDirection      Pointer to an array of dimension 3 containing the direction of the cylinder axis.
	CylinderRadiusMM      Radius of the cylinder.
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>The target surface must be provided as a reference point, a direction vector, and a radius. The reference point is a point on the cylinder mantle and represents the new coordinate origin of the target surface. In the cylinder cross-section it is the point with the largest z coordinate. The given direction is the direction of the cylinder axis, which will represent the x coordinate in the new coordinate system. The new y coordinate is the arc length distance on the cylinder mantle from the axis parallel to the cylinder direction going through the reference point.</li> <li>The new file should not be used for points outside the provided target surface.</li> <li><b>slcl_do_cylinder_calibration</b> requires parameters from the <b>Readme file</b>!</li> </ul>
Code example	See <b>Example.cpp</b> .
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_do_focus_calibration
Purpose	Category: <b>Calibration Optimization Functions</b> . Re-adjusts the 3d calibration based on measurements in the Z = 0 plane.
Function signature	<code>uint32_t slcl_do_focus_calibration( size_t Handle, uint16_t NPoints, const int32_t* XMeasurementBit, const int32_t* YMeasurementBit, int32_t* ZControlBit, const char* NewFilename )</code>
Argument(s)	Handle <b>Handle</b> of the <b>Correction</b> table that is to be changed.
	NPoints      Number of measured points.
	XMeasurementBit      Pointer to an array of dimension NPoints. This array must contain the measured x values: <ul style="list-style-type: none"> <li>• As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>• As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	YMeasurementBit      Pointer to an array of dimension NPoints. This array must contain the measured y values: <ul style="list-style-type: none"> <li>• As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>• As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	ZControlBit      Pointer to an array of dimension NPoints. This array must contain the measured Z-control values: <ul style="list-style-type: none"> <li>• As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>• As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	• –
Code example	See <b>Example.cpp</b> .
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_do_freeform_pointcloud_calibration
Purpose	Category: <b>Calibration Optimization Functions</b> . Recalculates a <b>3D-Correction file</b> for a user-defined free-form target surface that is defined by a point cloud.
Function signature	<code>uint32_t slcl_do_freeform_pointcloud_calibration( size_t Handle, uint32_t NPoints, const double* XValuesMM, const double* YValuesMM, const double* ZValuesMM, const char* NewFilename )</code>
Argument(s)	Handle      Handle of the <b>3D-Correction table</b> that is to be changed.
	NPoints      Number of points in the provided point cloud.
	XValuesMM      Pointer to an array of dimension NPoints. This array must contain the x coordinates of all the points in the point cloud.
	YValuesMM      Pointer to an array of dimension NPoints. This array must contain the y coordinates of all the points in the point cloud.
	ZValuesMM      Pointer to an array of dimension NPoints. This array must contain the z coordinates of all the points in the point cloud.
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions</b> , page 62.
Comment(s)	<ul style="list-style-type: none"> <li>The target surface must be provided as a series of points in 3d space. <b>slcl_do_freeform_pointcloud_calibration</b> interpolates between these points and adjust the <b>Correction table</b> so that the laser spot is always in focus on the given surface. Later, users need to command 2d positions to the RTC only – the focal shift is automatically adjusted. The coordinate system after the correction uses top view projection, meaning that X and Y are exactly the same as before.</li> <li><b>slcl_do_freeform_pointcloud_calibration</b> requires parameters from the <b>Readme file</b>!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–



Name of the function	slcl_do_plane_calibration
Purpose	Category: <b>Calibration Optimization Functions</b> . Recalculates a <b>3D-Correction table</b> for a new user-defined target plane that may be shifted, tilted, and rotated.
Function signature	<code>uint32_t slcl_do_plane_calibration( size_t Handle, const double* ReferencePointMM, const double* NewXDirection, const double* NewYDirection, const char* NewFilename )</code>
Argument(s)	Handle <b>Handle of the 3D-Correction table</b> that is to be changed. Must not be a <b>2D-Correction table</b> .
	ReferencePointMM      Pointer to an array of dimension 3. This array must contain a reference point for the new target plane. This point will be treated as the coordinate origin for the target plane.
	NewXDirection      Pointer to an array of dimension 3. This array must contain the new x direction in the target plane.
	NewYDirection      Pointer to an array of dimension 3. This array must contain the new y direction in the target plane. Must be perpendicular to NewXDirection.
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>The new target plane must be provided in parameter form with a reference point and two direction vectors. The reference point represents the new origin of the target plane, while the direction vectors represent the new x direction and y direction in the target plane. The direction vectors must be perpendicular.</li> <li>Depending on how much shifted and tilted the new target plane is compared to the original target plane, the <b>Correction file</b> may not be useful anymore for 3d-points that are not in the target plane. This cannot be remedied through further 3d-correction.</li> <li><b>slcl_do_plane_calibration</b> requires parameters from the <b>Readme file</b>!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_do_scale_calibration
Purpose	Category: <b>Calibration Optimization Functions</b> . Recalculates the <b>Correction table</b> using a new calibration factor that is provided by the user.
Function signature	<code>uint32_t slcl_do_scale_calibration( size_t Handle, uint32_t DesiredCalFactor, uint32_t* NewCalFactor, const char* NewFilename )</code>
Argument(s)	Handle <b>Handle of the Correction table</b> that is to be changed.
	DesiredCalFactor      The desired new calibration factor.
	NewCalFactor      The calibration factor that was ultimately used.
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li><b>slcl_do_scale_calibration</b> calculates the minimum calibration factor. It is allowed to provide a larger factor, but if it is smaller, the minimum calibration factor is used instead. If the provided factor is zero, the minimum calibration factor is used automatically.</li> <li><b>slcl_do_scale_calibration</b> requires parameters from the <b>Readme file</b>!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_do_stretch_calibration
Purpose	Category: <b>Calibration Optimization Functions</b> . Calculates the stretch factors for the selected table for a given set of target and measured positions.
Function signature	<code>uint32_t slcl_do_stretch_calibration( size_t Handle, uint16_t NPoints, const double* XTargetsMM, const double* YTargetsMM, const double* ZOffsetMM, const double* XMeasurementsMM, const double* YMeasurementsMM, const char* NewFilename, slcl_stretch_factors* CalculatedStretchFactors )</code>
Argument(s)	Handle <b>Handle</b> for the <b>Correction</b> table to be used. Its stretch factors will be modified by the function.
	NPoints      Number of measured points.
	XTargetsMM      Pointer to an array of dimension NPoints. This array must contain the targeted x values in mm.
	YTargetsMM      Pointer to an array of dimension NPoints. This array must contain the targeted y values in mm.
	ZOffsetMM      Pointer to an array of dimension NPoints. This array must contain the offset of the targeted Z-plane in mm.
	XMeasurementsMM      Pointer to an array of dimension NPoints. This array must contain the measured x values in mm.
	YMeasurementsMM      Pointer to an array of dimension NPoints. This array must contain the measured y values in mm.
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
	CalculatedStretchFactors      Pointer to the struct <code>slcl_stretch_factors</code> that the coefficients are written into.
Return value	See <b>Standard return values of CalibrationLibrary functions</b> , page 62.
Comment(s)	• –
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_enable_logging
Purpose	Category: <b>Administration Functions</b> . Enables CalibrationLibrary logging.
Function signature	<code>uint32_t slcl_enable_logging(void)</code>
Argument(s)	-
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>Logging is by default enabled after activation.</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	<b>slcl_disable_logging</b>

Name of the function	slcl_get_current_abc_coeffs
Purpose	Category: <b>Correction table Parameter Access Functions</b> . Returns the current coefficients of the ABC polynomial for the selected <b>Correction table</b> .
Function signature	<code>uint32_t slcl_get_current_abc_coeffs( size_t Handle, slcl_abc_pol_coefficients* CurrentCoeffs )</code>
Argument(s)	Handle <b>Handle for the Correction table to be used.</b>
	CurrentCoeffs <b>Pointer to struct <code>slcl_abc_pol_coefficients</code>.</b>
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>–</li> </ul>
Code example	See <b>Example.cpp</b> .
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	<code>slcl_get_current_calibration_factor</code>
Purpose	Category: <b>Correction table Parameter Access Functions</b> . Returns the current calibration factor of the selected <b>Correction table</b> .
Function signature	<code>uint32_t slcl_get_current_calibration_factor( size_t Handle, uint32_t* CurrentCalFactor )</code>
Argument(s)	Handle <b>Handle</b> for the desired <b>Correction table</b> .
	CurrentCalFactor <b>Pointer</b> to the variable that the calibration factor are written into.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>If the file is Ctb and not 3d, parameters from the <b>Readme file</b> are needed!</li> </ul>
Code example	See <b>Example.cpp</b> .
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	<code>slcl_get_current_stretch_factors</code>
Purpose	Category: <b>Correction table Parameter Access Functions</b> . Returns the current stretch factors of the selected <b>Correction table</b> .
Function signature	<code>uint32_t slcl_get_current_stretch_factors( size_t Handle, slcl_stretch_factors* CurrentStretchFactors )</code>
Argument(s)	Handle <b>Handle</b> for the <b>Correction table</b> to be used.
	CurrentStretchFactors <b>Pointer</b> to the struct <code>slcl_stretch_factors</code> in which the stretch factors are written into.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>–</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_get_lib_version
Purpose	Category: <b>Administration Functions</b> . Returns version info on the currently running CalibrationLibrary DLL.
Function signature	<code>VersionInfo slcl_get_lib_version(void)</code>
Argument(s)	-
Return value	See struct <code>VersionInfo</code> .
Comment(s)	• -
Code example	-
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	-

Name of the function	slcl_get_z_distance
Purpose	Category: <b>Correction table Evaluation Functions</b> . Returns the focal length for a given Point in the 3D volume.
Function signature	<code>uint32_t slcl_get_z_distance( size_t Handle, int32_t InputX, int32_t InputY, int32_t InputZ, int32_t* ZDistance );</code>
Argument(s)	Handle <b>Handle</b> for the <b>3D-Correction table</b> to be used. Must not be a <b>2D-Correction table</b> .
	InputX      x coordinate of the given point: <ul style="list-style-type: none"> <li>As 20-bit value, if the <b>Handle</b> is Ct5</li> <li>As 16-bit value, if the <b>Handle</b> is Ctb</li> </ul>
	InputY      y coordinate of the given point: <ul style="list-style-type: none"> <li>As 20-bit value, if the <b>Handle</b> is Ct5</li> <li>As 16-bit value, if the <b>Handle</b> is Ctb</li> </ul>
	InputZ      z coordinate of the given point: <ul style="list-style-type: none"> <li>As 20-bit value, if the <b>Handle</b> is Ct5</li> <li>As 16-bit value, if the <b>Handle</b> is Ctb</li> </ul>
	ZDistance      Pointer to the resulting value for the focal length: <ul style="list-style-type: none"> <li>As 20-bit value, if the <b>Handle</b> is Ct5</li> <li>As 16-bit value, if the <b>Handle</b> is Ctb</li> </ul>
Return value	See struct <b>VersionInfo</b> .
Comment(s)	<ul style="list-style-type: none"> <li>The returned <b>ZDistance</b> is the difference in focal length between the provided point (<b>InputX InputY InputZ</b>) and (0 0 0).</li> <li>If the calculation is impossible due to the input point being out of range for the system, a very large value are written into <b>ZDistance</b>.</li> <li><b>slcl_get_z_distance</b> and the RTC command <b>get_z_distance</b> are equivalent.</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_inverse_transform_points_2d
Purpose	Category: <b>Correction table Evaluation Functions</b> . Conduct an inverse 2d transformation using a <b>ct5-Correction table</b> .
Function signature	<code>uint32_t slcl_inverse_transform_points_2d( size_t Handle, uint32_t NPoints, const int32_t* InputX, const int32_t* InputY, int32_t* ResultX, int32_t* ResultY )</code>
Argument(s)	Handle <b>Handle</b> for the <b>ct5-Correction table</b> to be used.
	NPoints      Number of points to be transformed.
	InputX      Pointer to an array of dimension NPoints. This array must contain the x values as 20-bit values.
	InputY      Pointer to an array of dimension NPoints. This array must contain the y values as 20-bit values.
	ResultX      Pointer to an array of dimension NPoints. The results for X are written into this array as 20-bit values.
	ResultY      Pointer to an array of dimension NPoints. The results for Y are written into this array as 20-bit values.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>If the transformation is impossible due to the input points being out of range for the system, a very large value are written into each position of the output arrays for that set of measurements. All other points will still be attempted to be transformed normally. This function may also be called for a <b>3D-ct5-Correction table</b>, in which case the result is the intersection of the laser beam with the <math>z = 0</math> plane.</li> <li>The specified <b>Handle</b> table must be that of a <b>ct5-Correction table</b>. Inverse transformation is not available for <b>ctb-Correction tables</b>!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–



Name of the function	slcl_inverse_transform_points_2d_io
Purpose	Category: <b>Correction table Evaluation Functions</b> . Conduct an inverse 2d transformation using a <b>ct5-Correction table</b> .
Function signature	<code>uint32_t slcl_inverse_transform_points_2d_io( size_t Handle, uint32_t NPoints, int32_t* IOX, int32_t* IOY )</code>
Argument(s)	Handle <b>Handle</b> for the <b>ct5-Correction table</b> to be used.
	NPoints      Number of points to be transformed.
	IOX      Pointer to an array of dimension NPoints. This array must contain the x values. The results for X are written into this array as 20-bit values.
	IOY      Pointer to an array of dimension NPoints. This array must contain the y values. The results for Y are written into this array as 20-bit values.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>If the transformation is impossible due to the input points being out of range for the system, a very large value are written into each position of the output arrays for that set of measurements. All other points will still be attempted to be transformed normally. This function may also be called for a <b>3D-ct5-Correction table</b>, in which case the result is the intersection of the laser beam with the z=0 plane.</li> <li>The specified <b>Handle</b> table must be that of a <b>ct5-Correction table</b>. Inverse transformation is not available for <b>ctb-Correction tables</b>!</li> </ul>
Code example	See <b>Example.cpp</b> .
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_inverse_transform_points_3d
Purpose	Category: <b>Correction table Evaluation Functions</b> . Conduct an inverse 3d transformation using a <b>ct5-Correction table</b> .
Function signature	<code>uint32_t slcl_inverse_transform_points_3d( size_t Handle, uint32_t NPoints, const int32_t* InputX, const int32_t* InputY, const int32_t* InputZ, int32_t* ResultX, int32_t* ResultY, int32_t* ResultZ )</code>
Argument(s)	Handle <b>Handle</b> for the <b>3D-ct5-Correction table</b> to be used.
	NPoints      Number of points to be transformed.
	InputX      Pointer to an array of dimension NPoints. This array must contain the x values as 20-bit values.
	InputY      Pointer to an array of dimension NPoints. This array must contain the y values as 20-bit values.
	InputZ      Pointer to an array of dimension NPoints. This array must contain the z values as 20-bit values.
	ResultX      Pointer to an array of dimension NPoints. The results for X-are written into the array as 20-bit values.
	ResultY      Pointer to an array of dimension NPoints. The results for Y are written into the array as 20-bit values.
	ResultZ      Pointer to an array of dimension NPoints. The results for Z are written into the array as 20-bit values.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>If the transformation is impossible due to the input points being out of range for the system, a very large value are written into each position of the output arrays for that set of measurements. All other points will still be attempted to be transformed normally.</li> <li>The specified <b>Handle</b> table must be that of a <b>ct5-Correction table</b>. Inverse transformation is not available for <b>ctb-Correction tables</b>!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_inverse_transform_points_3d_fixed_z														
Purpose	<p>Category: <b>Correction table Evaluation Functions</b>.</p> <p>Conduct an inverse 3d transformation using a <b>ct5-Correction table</b> and a fixed Z-value in the working field.</p>														
Function signature	<pre>uint32_t slcl_inverse_transform_points_3d_fixed_z( size_t Handle, uint32_t NPoints, const int32_t* InputX, const int32_t* InputY, const int32_t* ImageFieldZ, int32_t* ResultX, int32_t* ResultY );</pre>														
Argument(s)	<table> <tr> <td>Handle</td><td><b>Handle</b> for the <b>ct5-Correction table</b> to be used.</td></tr> <tr> <td>NPoints</td><td>Number of points to be transformed.</td></tr> <tr> <td>InputX</td><td>Pointer to an array of dimension NPoints. This array must contain the x values as 20-bit values.</td></tr> <tr> <td>InputY</td><td>Pointer to an array of dimension NPoints. This array must contain the y values as 20-bit values.</td></tr> <tr> <td>ImageFieldZ</td><td>Pointer to an array of dimension NPoints. This array must contain the z coordinates in the working field as 20-bit values.</td></tr> <tr> <td>ResultX</td><td>Pointer to an array of dimension NPoints. The results for X-are written into the array as 20-bit values.</td></tr> <tr> <td>ResultY</td><td>Pointer to an array of dimension NPoints. The results for Y-are written into the array as 20-bit values.</td></tr> </table>	Handle	<b>Handle</b> for the <b>ct5-Correction table</b> to be used.	NPoints	Number of points to be transformed.	InputX	Pointer to an array of dimension NPoints. This array must contain the x values as 20-bit values.	InputY	Pointer to an array of dimension NPoints. This array must contain the y values as 20-bit values.	ImageFieldZ	Pointer to an array of dimension NPoints. This array must contain the z coordinates in the working field as 20-bit values.	ResultX	Pointer to an array of dimension NPoints. The results for X-are written into the array as 20-bit values.	ResultY	Pointer to an array of dimension NPoints. The results for Y-are written into the array as 20-bit values.
Handle	<b>Handle</b> for the <b>ct5-Correction table</b> to be used.														
NPoints	Number of points to be transformed.														
InputX	Pointer to an array of dimension NPoints. This array must contain the x values as 20-bit values.														
InputY	Pointer to an array of dimension NPoints. This array must contain the y values as 20-bit values.														
ImageFieldZ	Pointer to an array of dimension NPoints. This array must contain the z coordinates in the working field as 20-bit values.														
ResultX	Pointer to an array of dimension NPoints. The results for X-are written into the array as 20-bit values.														
ResultY	Pointer to an array of dimension NPoints. The results for Y-are written into the array as 20-bit values.														
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .														
Comment(s)	<ul style="list-style-type: none"> <li>If the transformation is impossible due to the input points being out of range for the system, a very large value are written into each position of the output arrays for that set of measurements. All other points will still be attempted to be transformed normally.</li> <li>The specified <b>Handle</b> table must be that of a <b>ct5-Correction table</b>. Inverse transformation is not available for <b>ctb-Correction tables</b>!</li> </ul>														
Code example	–														
Version info	Available as of CalibrationLibrary DLL V1.0.0.														
References	–														

Name of the function	slcl_inverse_transform_points_3d_fixed_z_io
Purpose	Category: <b>Correction table Evaluation Functions</b> . Conduct an inverse 3d transformation using a <b>ct5-Correction table</b> , using a fixed z-value in the working field.
Function signature	<code>uint32_t slcl_inverse_transform_points_3d_fixed_z_io( size_t Handle, uint32_t NPoints, int32_t* IOX, int32_t* IOY, const int32_t* ImageFieldZ );</code>
Argument(s)	Handle <b>Handle</b> for the <b>ct5-Correction table</b> to be used.
	NPoints      Number of points to be transformed.
	IOX      Pointer to an array of dimension NPoints. This array must contain the x values. The results for X are written into the array as 20-bit values.
	IOY      Pointer to an array of dimension NPoints. This array must contain the y values. The results for Y are written into the array as 20-bit values.
	ImageFieldZ      Pointer to an array of dimension NPoints. This array must contain the z coordinates in the working field as 20-bit values.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>If the transformation is impossible due to the input points being out of range for the system, a very large value are written into each position of the output arrays for that set of measurements. All other points will still be attempted to be transformed normally.</li> <li>The specified <b>Handle</b> table must be that of a <b>ct5-Correction table</b>. Inverse transformation is not available for <b>ctb-Correction tables</b>!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_inverse_transform_points_3d_io
Purpose	Category: <b>Correction table Evaluation Functions</b> . Conduct an inverse 3d transformation using a <b>ct5-Correction table</b> .
Function signature	<code>uint32_t slcl_inverse_transform_points_3d_io( const size_t Handle, const uint32_t NPoints, int32_t* IOX, int32_t* IOY, int32_t* IOZ )</code>
Argument(s)	Handle <b>Handle</b> for the <b>3D-ct5-Correction table</b> to be used.
	NPoints      Number of points to be transformed.
	IOX      Pointer to an array of dimension NPoints. This array must contain the x values. The results for X are written into the array as 20-bit values.
	IOY      Pointer to an array of dimension NPoints. This array must contain the y values. The results for Y are written into the array as 20-bit values.
	IOZ      Pointer to an array of dimension NPoints. This array must contain the z values. The results for Z are written into the array as 20-bit values.
Return value	See <b>Standard return values of CalibrationLibrary functions</b> , page 62.
Comment(s)	<ul style="list-style-type: none"> <li>If the transformation is impossible due to the input points being out of range for the system, a very large value are written into each position of the output arrays for that set of measurements. All other points will still be attempted to be transformed normally.</li> <li>The specified <b>Handle</b> table must be that of a <b>ct5-Correction table</b>. Inverse transformation is not available for <b>ctb-Correction tables</b>!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_inverse_transform_points_3d_io_with_trafos
Purpose	Category: <b>Correction table Evaluation Functions</b> . Conduct an inverse 3d transformation using a <b>ct5-Correction table</b> .
Function signature	<pre>uint32_t slcl_inverse_transform_points_3d_io_with_trafos( const size_t Handle, const slcl_additional_transformations* AdditionalTrafos, const uint32_t NPoints, uint32_t* IOX, uint32_t* IOY, uint32_t* IOZ);</pre>
Argument(s)	Handle <b>Handle</b> for the <b>3D-ct5-Correction table</b> to be used.
	AdditionalTrafos Additional transformations to take into account. See struct <b>slcl_additional_transformations</b> .
	NPoints Number of points to be transformed.
	IOX Pointer to an array of dimension NPoints. This array must contain the x values. The results for X are written into the array as 20-bit values.
	IOY Pointer to an array of dimension NPoints. This array must contain the y values. The results for Y are written into the array as 20-bit values.
	IOZ Pointer to an array of dimension NPoints. This array must contain the z values. The results for Z are written into the array as 20-bit values.
Return value	See <b>Standard return values of CalibrationLibrary functions</b> , page 62.
Comment(s)	<ul style="list-style-type: none"> <li>If the transformation is impossible due to the input points being out of range for the system, a very large value are written into each position of the output arrays for that set of measurements. All other points will still be attempted to be transformed normally.</li> <li>The specified <b>Handle</b> table must be that of a <b>ct5-Correction table</b>. Inverse transformation is not available for <b>ctb-Correction tables</b>!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.1.0.
References	–

Name of the function	slcl_inverse_transform_points_3d_with_trafos
Purpose	Category: <b>Correction table Evaluation Functions</b> . Conduct an inverse 3d transformation using a <b>ct5-Correction table</b> .
Function signature	<pre>uint32_t slcl_inverse_transform_points_3d_with_trafos( size_t Handle, const slcl_additional_transformations* AdditionalTrafos, uint32_t NPoints, const int32_t* InputX, const int32_t* InputY, const int32_t* InputZ, int32_t* ResultX, int32_t* ResultY, int32_t* ResultZ);</pre>
Argument(s)	Handle <b>Handle</b> for the <b>3D-ct5-Correction table</b> to be used.
	AdditionalTrafos <b>Additional transformations to take into account.</b> See struct <b>slcl_additional_transformations</b> .
	NPoints <b>Number of points to be transformed.</b>
	InputX <b>Pointer to an array of dimension NPoints.</b> This array must contain the x values as 20-bit values.
	InputY <b>Pointer to an array of dimension NPoints.</b> This array must contain the y values as 20-bit values.
	InputZ <b>Pointer to an array of dimension NPoints.</b> This array must contain the z values as 20-bit values.
	ResultX <b>Pointer to an array of dimension NPoints.</b> The results for X are written into the array as 20-bit values.
	ResultY <b>Pointer to an array of dimension NPoints.</b> The results for Y are written into the array as 20-bit values.
	ResultZ <b>Pointer to an array of dimension NPoints.</b> The results for Z are written into the array as 20-bit values.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>If the transformation is impossible due to the input points being out of range for the system, a very large value are written into each position of the output arrays for that set of measurements. All other points will still be attempted to be transformed normally.</li> <li>The specified <b>Handle</b> table must be that of a <b>ct5-Correction table</b>. Inverse transformation is not available for <b>ctb-Correction tables</b>!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.1.0.
References	–

Name of the function	<code>slcl_load_correction_table</code>
Purpose	Category: <b>Administration Functions</b> . Initializes a <b>Handle</b> from the specified file name.
Function signature	<code>uint32_t slcl_load_correction_table( size_t* Handle, const char* CorrFilename, const char* ReadMeFilename )</code>
Argument(s)	<code>Handle</code> Memory address of the newly created <b>Correction table Handle</b> .
	<code>CorrFilename</code> Name of the desired <b>Correction file</b> .
	<code>ReadMeFilename</code> Name of the corresponding <b>Readme file</b> . If null, the <b>Readme file</b> is assumed to be in the same folder as the <b>Correction file</b> , that it has the exact same name as the <b>Correction file</b> , appended by " <code>_ReadMe</code> " (for <b>ctb-Correction files</b> ) or " <code>_ct5_ReadMe</code> " (for <b>ct5-Correction files</b> ), and that its extension is " <code>*.txt</code> ".
Return value	See <b>Standard return values of CalibrationLibrary functions</b> , page 62.
Comment(s)	<ul style="list-style-type: none"> <li><code>slcl_load_correction_table</code> creates a new <b>Correction table</b> object and returns a <b>Handle</b> to interface with it. If <code>slcl_load_correction_table</code> fails, the <b>Handle</b> is set to 0 and no instance is created.</li> <li>It is also possible to provide a path for the <b>Readme file</b> belonging to the <b>Correction file</b>. Information from this <b>Readme file</b> are needed (for calculations) by: <ul style="list-style-type: none"> <li><code>slcl_convert_ctb_to_ct5</code></li> <li><code>slcl_do_scale_calibration</code></li> <li><code>slcl_do_beam_tilt_calibration</code></li> </ul> in particular, in case of <b>2D-ctb-Correction tables</b> <ul style="list-style-type: none"> <li><code>slcl_get_current_calibration_factor</code></li> <li><code>slcl_xy_calibration_mm_targets</code></li> <li><code>slcl_xy_calibration_mm_targets_callback</code></li> </ul> </li> </ul>
Code example	See <b>Example.cpp</b> .
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	<code>slcl_delete_correction_table_handle</code>



Name of the function	slcl_save_correction_table
Purpose	Category: <b>Administration Functions</b> Saves the specified <b>Handle</b> as a file.
Function signature	<code>uint32_t slcl_save_correction_table( size_t Handle, const char* NewFilename )</code>
Argument(s)	Handle <b>Handle</b> for the <b>Correction table</b> .
	NewFilename              Name of the file that the result shall be saved to.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>If the table contains a valid <b>Readme filename</b>, a new <b>Readme file</b> will be generated as well.</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_set_abc_manually
Purpose	Category: <b>Correction table Parameter Access Functions</b> . Manually sets the ABC coefficients for the selected <b>Handle</b> to given values and then saves it as a file.
Function signature	<code>uint32_t slcl_set_abc_manually( size_t Handle, const slcl_abc_pol_coefficients* NewCoeffs, const char* NewFilename )</code>
Argument(s)	Handle <b>Handle</b> for the <b>Correction table</b> whose ABC coefficients shall be changed.
	NewCoeffs                  Pointer to the struct <b>slcl_abc_pol_coefficients</b> that the coefficients are written into.
	NewFilename              Name of the file that the result shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>–</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	<code>slcl_set_ct5_parameters_manually</code>
Purpose	Category: <b>Administration Functions</b> . Supplies the needed parameters from the <b>Readme file</b> manually for a <b>ct5-Correction file</b> .
Function signature	<code>uint32_t slcl_set_ct5_parameters_manually( size_t Handle, const slcl_ct5_table_readme_parameters* Params, const char* NewFilename )</code>
Argument(s)	Handle <b>Handle</b> for the <b>ct5-Correction table</b> to be improved.
	Params      Pointer to the struct <code>slcl_ct5_table_readme_parameters</code> .
	NewFilename      Name of the file that the result shall be saved to.
Return value	See <b>Standard return values of CalibrationLibrary functions</b> , page 62.
Comment(s)	<ul style="list-style-type: none"> <li>For ct5 beam tilt correction, the z-range (for 3D systems) and the lens distortion coefficients (for systems with f-theta objective) are needed. These parameters normally must be read from the <b>Readme file</b>. If there is no <b>Readme file</b> available, but the necessary parameters are known, they can be supplied by <b>slcl_set_ct5_parameters_manually</b>.</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	<code>slcl_set_stretch_factors_manually</code>
Purpose	Category: <b>Correction table Parameter Access Functions</b> . Manually sets the stretch factors for the selected <b>Correction table</b> to given values.
Function signature	<code>uint32_t slcl_set_stretch_factors_manually( size_t Handle, const slcl_stretch_factors* NewStretchFactors, const char* NewFilename )</code>
Argument(s)	Handle <b>Handle</b> for the <b>Correction table</b> whose stretch factors shall be changed.
	NewStretchFactors      Pointer to the struct <code>slcl_stretch_factors</code> containing the new stretch factors.
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions</b> , page 62.
Comment(s)	<ul style="list-style-type: none"> <li>–</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_transform_points_2d
Purpose	Category: <b>Correction table Evaluation Functions</b> . Conduct a forward 2d transformation using a <b>Correction table</b> .
Function signature	<code>uint32_t slcl_transform_points_2d( size_t Handle, uint32_t NPoints, const int32_t* InputX, const int32_t* InputY, int32_t* ResultX, int32_t* ResultY )</code>
Argument(s)	Handle <b>Handle</b> for the <b>Correction table</b> to be used.
	NPoints      Number of points to be transformed.
	InputX      Pointer to an array of dimension NPoints. This array must contain the x values: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	InputY      Pointer to an array of dimension NPoints. This array must contain the y values: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	ResultX      Pointer to an array of dimension NPoints. The results for X are written into the array: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	ResultY      Pointer to an array of dimension NPoints. The results for Y are written into the array: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>If the transformation is impossible due to the input points being out of range for the system, a very large value are written into each position of the output arrays for that set of measurements. All other points will still be attempted to be transformed normally.</li> <li><b>slcl_transform_points_2d</b> may also be called for a <b>3D-Correction table</b> in which case it is assumed that the desired z value is 0.</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_transform_points_2d_io
Purpose	Category: <b>Correction table Evaluation Functions</b> . Conduct a forward 2d transformation using a <b>Correction table</b> .
Function signature	<code>uint32_t slcl_transform_points_2d_io( size_t Handle, uint32_t NPoints, int32_t* IOX, int32_t* IOY )</code>
Argument(s)	Handle <b>Handle</b> for the <b>Correction table</b> to be used.
	NPoints      Number of points to be transformed.
	IOX      Pointer to an array of dimension NPoints. This array must contain the x values. The results for X are written into the array: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	IOY      Pointer to an array of dimension NPoints. This array must contain the y values. The results for Y are written into the array: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
Return value	See <b>Standard return values of CalibrationLibrary functions</b> , page 62.
Comment(s)	<ul style="list-style-type: none"> <li>If the transformation is impossible due to the input points being out of range for the system, a very large value are written into each position of the output arrays for that set of measurements. All other points will still be attempted to be transformed normally. This function may also be called for a 3d-table, in which case it is assumed that the desired z value is zero.</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_transform_points_3d
Purpose	Category: <b>Correction table Evaluation Functions</b> . Conduct a forward 3d transformation using a <b>Correction table</b> .
Function signature	<code>uint32_t slcl_transform_points_3d( size_t Handle, uint32_t NPoints, const int32_t* InputX, const int32_t* InputY, const int32_t* InputZ, int32_t* ResultX, int32_t* ResultY, int32_t* ResultZ )</code>
Argument(s)	Handle <b>Handle</b> for the <b>3D-Correction table</b> to be used.
	NPoints      Number of points to be transformed.
	InputX      Pointer to an array of dimension NPoints. This array must contain the x values: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	InputY      Pointer to an array of dimension NPoints. This array must contain the y values: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	InputZ      Pointer to an array of dimension NPoints. This array must contain the y values: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	ResultX      Pointer to an array of dimension NPoints. The results for X are written into the array: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	ResultY      Pointer to an array of dimension NPoints. The results for Y are written into the array: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	ResultZ      Pointer to an array of dimension NPoints. The results for Z are written into the array: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>If the transformation is impossible due to the input points being out of range for the system, a very large value are written into each position of the output arrays for that set of measurements. All other points will still be attempted to be transformed normally.</li> </ul>
Code example	See <b>Example.cpp</b> .
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_transform_points_3d_io
Purpose	Category: <b>Correction table Evaluation Functions</b> . Conduct a forward 3d transformation using a <b>Correction table</b> .
Function signature	<code>uint32_t slcl_transform_points_3d_io( size_t Handle, uint32_t NPoints, int32_t* IOX, int32_t* IOY, int32_t* IOZ )</code>
Argument(s)	Handle <b>Handle</b> for the <b>3D-Correction table</b> to be used.
	NPoints      Number of points to be transformed.
	IOX      Pointer to an array of dimension NPoints. This array must contain the x values. The results for X are written into the array: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	IOY      Pointer to an array of dimension NPoints. This array must contain the y values. The results for Y are written into the array: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	IOZ      Pointer to an array of dimension NPoints. This array must contain the z values. The results for Z are written into the array: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>If the transformation is impossible due to the input points being out of range for the system, a very large value are written into each position of the output arrays for that set of measurements. All other points will still be attempted to be transformed normally.</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_xy_calibration_bit_targets
Purpose	Category: <b>Calibration Optimization Functions</b> . Recalculates the values of the X- and Y-tables as well as the inverse X- and Y-tables (for Ct5) based on a given input of target points and measured points.
Function signature	<code>uint32_t slcl_xy_calibration_bit_targets( size_t Handle, uint16_t NPoints, const int32_t* XTargetsBit, const int32_t* YTargetsBit, const double* XMeasurementsMM, const double* YMeasurementsMM, const slcl_xy_calibration_settings* OtherParameters, slcl_xy_calibration_interpolation_results* InterpolationResults, const char* NewFilename )</code>
Argument(s)	Handle <b>Handle</b> for the <b>Correction table</b> to be improved.
	NPoints      Number of measured points.
	XTargetsBit      Pointer to an array of dimension NPoints. This array must contain the targeted x values: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	YTargetsBit      Pointer to an array of dimension NPoints. This array must contain targeted y values: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	XMeasurementsMM      Pointer to an array of dimension NPoints. This array must contain the measured x values in mm.
	YMeasurementsMM      Pointer to an array of dimension NPoints. This array must contain the measured y values in mm.
	OtherParameters      Pointer to a struct <code>slcl_xy_calibration_settings</code> . This struct must contain the parameters for the interpolation.
	InterpolationResults      Pointer to a struct <code>slcl_xy_calibration_interpolation_results</code> . This struct must contain additional information about the interpolation results.
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions</b> , page 62.
Comment(s)	• –
Code example	<a href="#">Example.cpp</a>
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_xy_calibration_bit_targets_callback
Purpose	Category: <b>Calibration Optimization Functions</b> . Recalculates the values of the X- and Y-tables as well as the inverse X- and Y-tables (for Ct5) based on a given input of target points and measured points.
Function signature	<code>uint32_t slcl_xy_calibration_bit_targets_callback( size_t Handle, uint16_t NPoints, const int32_t* XTargetsBit, const int32_t* YTargetsBit, const double* XMeasurementsMM, const double* YMeasurementsMM, const slcl_xy_calibration_settings* OtherParameters, slcl_xy_calibration_interpolation_results* InterpolationResults, void (*Callback)(const char*, uint32_t, void*) Callback, void* Context, const char* NewFilename )</code>
Argument(s)	Handle <b>Handle</b> for the <b>Correction</b> table to be improved.
	NPoints      Number of measured points.
	XTargetsBit      Pointer to an array of dimension NPoints. This array must contain the targeted x values: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	YTargetsBit      Pointer to an array of dimension NPoints. This array must contain the targeted y values: <ul style="list-style-type: none"> <li>As 20-bit values, if the <b>Handle</b> is Ct5</li> <li>As 16-bit values, if the <b>Handle</b> is Ctb</li> </ul>
	XMeasurementsMM      Pointer to an array of dimension NPoints. This array must contain the measured x values in mm.
	YMeasurementsMM      Pointer to an array of dimension NPoints. This array must contain the measured y values in mm.
	OtherParameters      Pointer to struct <code>slcl_xy_calibration_settings</code> containing the parameters for the interpolation.
	InterpolationResults      Pointer to struct <code>slcl_xy_calibration_interpolation_results</code> containing additional information about the interpolation results.
	Callback      Function pointer to a <b>Callback function</b> which informs about the progress of the calculation. It contains a message, a progress percentage value, and a context pointer.
	Context      Pointer to the context of the <b>Callback function</b> .
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions</b> , page 62.
Comment(s)	• –
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–



Name of the function	<code>slcl_xy_calibration_mm_targets</code>
Purpose	Category: <b>Calibration Optimization Functions</b> . Recalculates the values of the X- and Y-tables as well as the inverse X- and Y-tables (for Ct5) based on a given input of target points and measured points.
Function signature	<code>uint32_t slcl_xy_calibration_mm_targets( size_t Handle, uint16_t NPoints, const double* XTargetsMM, const double* YTargetsMM, const double* XMeasurementsMM, const double* YMeasurementsMM, const slcl_xy_calibration_settings* OtherParameters, slcl_xy_calibration_interpolation_results* InterpolationResults, const char* NewFilename )</code>
Argument(s)	Handle <b>Handle</b> for the <b>Correction table</b> to be improved.
	NPoints      Number of measured points.
	XTargetsMM      Pointer to an array of dimension NPoints. This array must contain the targeted x values in mm.
	YTargetsMM      Pointer to an array of dimension NPoints. This array must contain the targeted y values in mm.
	XMeasurementsMM      Pointer to an array of dimension NPoints. This array must contain the measured x values in mm.
	YMeasurementsMM      Pointer to an array of dimension NPoints. This array must contain the measured y values in mm.
	OtherParameters      Pointer to a struct <code>slcl_xy_calibration_settings</code> containing the parameters for the interpolation.
	InterpolationResults      Pointer to a struct <code>slcl_xy_calibration_interpolation_results</code> containing additional information about the interpolation results.
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions</b> , page 62.
Comment(s)	<ul style="list-style-type: none"> <li>If the file is Ctb and not 3d, parameters from the <b>Readme file</b> are needed!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

Name of the function	slcl_xy_calibration_mm_targets_callback
Purpose	Category: <b>Calibration Optimization Functions</b> . Recalculates the values of the X- and Y-tables as well as the inverse X- and Y-tables (for Ct5) based on a given input of target points and measured points.
Function signature	<pre>uint32_t slcl_xy_calibration_mm_targets_callback( size_t Handle, uint16_t NPoints, const double* XTargetsMM, const double* YTargetsMM, const double* XMeasurementsMM, const double* YMeasurementsMM, const slcl_xy_calibration_settings* OtherParameters, slcl_xy_calibration_interpolation_results* InterpolationResults, void (*Callback)(const char*, uint32_t, void*) Callback, void* Context, const char* NewFilename )</pre>
Argument(s)	Handle <b>Handle</b> for the <b>Correction table</b> to be improved.
	NPoints      Number of measured points.
	XTargetsMM      Pointer to an array of dimension NPoints. This array must contain the targeted x values in mm.
	YTargetsMM      Pointer to an array of dimension NPoints. This array must contain the targeted y values in mm.
	XMeasurementsMM      Pointer to an array of dimension NPoints. This array must contain the measured x values in mm.
	YMeasurementsMM      Pointer to an array of dimension NPoints. This array must contain the measured y values in mm.
	OtherParameters      Pointer to a struct containing the parameters for the interpolation.
	InterpolationResults      Pointer to a struct containing additional information about the interpolation results.
	Callback      Function pointer to a callback function which informs about the progress of the calculation. It contains a message, a progress percentage value, and a context pointer.
	Context      Pointer to the context of the callback function.
	NewFilename      Name of the file that the result shall be saved to. If NULL, the result is not saved.
Return value	See <b>Standard return values of CalibrationLibrary functions, page 62</b> .
Comment(s)	<ul style="list-style-type: none"> <li>If the file is Ctb and not 3d, parameters from the <b>Readme file</b> are needed!</li> </ul>
Code example	–
Version info	Available as of CalibrationLibrary DLL V1.0.0.
References	–

## 4 Structures struct

In this Chapter:

- struct **slcl\_abc\_pol\_coefficients**
- struct **slcl\_additional\_transformations**
- struct **slcl\_ct5\_table\_readme\_parameters**
- struct **slcl\_stretch\_factors**
- struct **slcl\_xy\_calibration\_interpolation\_results**
- struct **slcl\_xy\_calibration\_settings**
- struct **VersionInfo**

Name of the structure	slcl_abc_pol_coefficients		
Description	This structure defines: <ul style="list-style-type: none"> <li>• The coefficients of an ABC polynomial</li> </ul>		
Used by	This structure is used with: <ul style="list-style-type: none"> <li>• <b>slcl_get_current_abc_coeffs</b></li> <li>• <b>slcl_do_abc_calibration</b></li> <li>• <b>slcl_set_abc_manually</b></li> </ul>		
Syntax	<pre>struct slcl_abc_pol_coefficients {     double      OffsetTermA;     double      LinTermB;     double      QuadTermC; };</pre>		
Argument(s)	double	OffsetTermA	Offset coefficient A.
	double	LinTermB	Linear coefficient B.
	double	QuadTermC	Square coefficient C.
Comment(s)	<ul style="list-style-type: none"> <li>• –</li> </ul>		
Version info	Available as of CalibrationLibrary DLL V1.0.0.		

Name of the structure	slcl_additional_transformations		
Description	<p>This structure defines:</p> <ul style="list-style-type: none"><li>Parameters for “additional” transformations That is, for calculating also such transformations which otherwise can be done only by means of RTC commands (on top of the <b>Correction file</b> transformation).</li></ul>		
Used by	<p>This structure is used with:</p> <ul style="list-style-type: none"><li><b>slcl_inverse_transform_points_3d_io_with_trafos</b></li><li><b>slcl_inverse_transform_points_3d_with_trafos</b></li></ul>		
Syntax	<pre>struct slcl_additional_transformations {     double      PreOffsetX;     double      PreOffsetY;     double      GainX;     double      GainY;     double      Defocus;     double      PostOffsetX;     double      PostOffsetY;     double      PostOffsetZ;     double      MatrixXX;     double      MatrixXY;     double      MatrixYX;     double      MatrixYY; };</pre>		
Argument(s)	double	PreOffsetX	Before <b>Correction file</b> transformation: Added to <b>InputX</b>
	double	PreOffsetY	Before <b>Correction file</b> transformation: Added to <b>InputY</b> .
	double	GainX	Before <b>Correction file</b> transformation: Multiplied with the resulting x value.
	double	GainY	Before <b>Correction file</b> transformation: Multiplied with the resulting y value.
	double	Defocus	During <b>Correction file</b> transformation: Subtracted from the focal shift.
	double	PostOffsetX	After <b>Correction file</b> transformation: Added to <b>ResultX</b> .
	double	PostOffsetY	After <b>Correction file</b> transformation: Added to <b>ResultY</b> .
	double	PostOffsetZ	After <b>Correction file</b> transformation: Added to <b>ResultZ</b> .

Name of the structure	slcl_additional_transformations		
Argument(s) (cont'd)	double	MatrixXX	x Matrix coefficient by which the resulting x value is multiplied.
	double	MatrixXY	x Matrix coefficient by which the resulting y value is multiplied.
	double	MatrixYX	y Matrix coefficient by which the resulting x value is multiplied.
	double	MatrixYY	y Matrix coefficient by which the resulting y value is multiplied.
Comment(s)	• –		
Version info	Available as of CalibrationLibrary DLL V1.1.0.		

Name of the structure	slcl_ct5_table_readme_parameters	
Description	This structure defines: <ul style="list-style-type: none"> <li>Extra parameters needed for certain calibration tools for <b>ct5-Correction files</b></li> </ul>	
Used by	This structure is used with: <ul style="list-style-type: none"> <li><b>slcl_set_ct5_parameters_manually</b></li> </ul>	
Syntax	<pre>struct slcl_ct5_table_readme_parameters {     double      ZRange;     double      F1;     double      F2;     double      F3;     double      F4; };</pre>	
Argument(s)	double            ZRange	Z-Range of the system. Corresponds to the "Max. Z-Range" entry in the <b>ct5 Readme file</b> .
	double            F1	Distortion coefficient of the f-theta objective. Corresponds to the "f1" entry in the <b>ct5 Readme file</b> .
	double            F2	Distortion coefficient of the f-theta objective. Corresponds to the "f2" entry in the <b>ct5 Readme file</b> .
	double            F3	Distortion coefficient of the f-theta objective. Corresponds to the "f3" entry in the <b>ct5 Readme file</b> .
	double            F4	Distortion coefficient of the f-theta objective. Corresponds to the "f4" entry in the <b>ct5 Readme file</b> .
Comment(s)	<ul style="list-style-type: none"> <li>–</li> </ul>	
Version info	Available as of CalibrationLibrary DLL V1.0.0.	

Name of the structure	slcl_stretch_factors		
Description	This structure defines: <ul style="list-style-type: none"> <li>The 2 values for the stretch factors</li> </ul>		
Used by	This structure is used with: <ul style="list-style-type: none"> <li><b>slcl_do_stretch_calibration</b></li> <li><b>slcl_get_current_stretch_factors</b></li> <li><b>slcl_set_stretch_factors_manually</b></li> </ul>		
Syntax	<pre>struct slcl_stretch_factors {     double          XStretchFactor;     double          YStretchFactor; };</pre>		
Argument(s)	double	XStretchFactor	Stretch factor in x direction.
	double	YStretchFactor	Stretch factor in y direction.
Comment(s)	<ul style="list-style-type: none"> <li>–</li> </ul>		
Version info	Available as of CalibrationLibrary DLL V1.0.0.		

Name of the structure	slcl_xy_calibration_interpolation_results		
Description	This structure defines: <ul style="list-style-type: none"><li>• Extra information about the results of the interpolation</li></ul>		
Used by	This structure is used with: <ul style="list-style-type: none"><li>• <b>slcl_xy_calibration_bit_targets</b></li><li>• <b>slcl_xy_calibration_bit_targets_callback</b></li><li>• <b>slcl_xy_calibration_mm_targets</b></li><li>• <b>slcl_xy_calibration_mm_targets_callback</b></li></ul>		
Syntax	<pre>struct slcl_xy_calibration_interpolation_results {     double          MaxDeviationOverallMM;     double          StdDeviationOverallMM;     double          StdDeviationXMM;     double          StdDeviationYMM;     double          RegularizationFactor;     double          NewXMinMM;     double          NewXMaxMM;     double          NewYMinMM;     double          NewYMaxMM;     uint32_t        MaxPolyOrder;     uint32_t        GalvoLimitsReached; };</pre>		
Argument(s)	double	MaxDeviationOverallMM	Largest deviation of the interpolation fit to any one measured point.
	double	StdDeviationOverallMM	Standard deviation of the measured points to the interpolation fit.
	double	StdDeviationXMM	Standard deviation of the measured points to the interpolation fit for the x coordinate only.
	double	StdDeviationYMM	Standard deviation of the measured points to the interpolation fit for the y coordinate only.
	double	RegularizationFactor	Regularization factor used for the thin plate spline interpolation.
	double	NewXMinMM	Left-most coordinate of the calculated working field.
	double	NewXMaxMM	Right-most coordinate of the calculated working field.
	double	NewYMinMM	Bottom coordinate of the calculated working field.
	double	NewYMaxMM	Top coordinate of the calculated working field.



Name of the structure	slcl_xy_calibration_interpolation_results		
Argument(s) (cont'd)	uint32_t	MaxPolyOrder	Degree of the base polynomial used for interpolation.
	uint32_t	GalvoLimitsReached	If the galvanometer scanner limits are reached during the calculation of the x table and y table, this is set to 1, otherwise 0.
Comment(s)	• –		
Version info	Available as of CalibrationLibrary DLL V1.0.0.		

Name of the structure	slcl_xy_calibration_settings		
Description	<p>This structure defines:</p> <ul style="list-style-type: none"> <li>This structure defines extra parameters for <b>XY Calibration</b></li> </ul>		
Used by	<p>This structure is used with:</p> <ul style="list-style-type: none"> <li><b>slcl_xy_calibration_bit_targets</b></li> <li><b>slcl_xy_calibration_bit_targets_callback</b></li> <li><b>slcl_xy_calibration_mm_targets</b></li> <li><b>slcl_xy_calibration_mm_targets_callback</b></li> </ul>		
Syntax	<pre>struct slcl_xy_calibration_settings {     uint32_t      XYCalibrationOptions;     uint32_t      NewCalibrationFactor;     double        RestrictionScaling;     double        ToleranceUM;     uint32_t      MaxFitOrder; };</pre>		
Argument(s)	uint32_t	XYCalibrationOptions	Bit field containing <b>slcl_xy_calibration_options</b> .
	uint32_t	NewCalibrationFactor	The desired calibration factor for the new file. Irrelevant if <b>slcl_xy_calibration_options</b> <b>SET_MANUAL_CALIBRATION</b> is not set. If it is set and <b>NewCalibrationFactor</b> is 0, the calibration factor is automatically adjusted to the smallest value that does not exceed galvanometer scanner limits.
	double	RestrictionScaling	Factor by which the restricted area is enlarged. Irrelevant if <b>slcl_xy_calibration_options</b> <b>RESTRICT_CORRECTION_FILE</b> is not set in <b>XYCalibrationOptions</b> .
	double	ToleranceUM	Distance by which the interpolation fit may deviate from the measured points. In $\mu\text{m}$ . Irrelevant if <b>slcl_xy_calibration_options</b> <b>USE_AUTO_TOLERANCE</b> is set in <b>XYCalibrationOptions</b> .

Name of the structure	slcl_xy_calibration_settings		
Argument(s) (cont'd)	uint32_t	MaxFitOrder	<p>≥ V1.4.0. Only relevant, if <code>USE_MAX_FIT_ORDER</code> from enum <code>slcl_xy_calibration_options</code> is set.</p> <p>The highest degree of the base polynomial to be used for interpolation. Allowed values: 1...9 (default value). Other values are interpreted as '9'.</p> <p>Background: With xy calibration, CalibrationLibrary DLL performs an interpolation. A polynomial is determined as part of this interpolation. Its degree can be at most 9. By <code>MaxFitOrder</code>, the possible degree can even be set lower. The finally determined polynomial degree is returned by <code>MaxPolyOrder</code> from struct <code>slcl_xy_calibration_interpolation_results</code>. Accordingly, the following applies: <math>\text{MaxPolyOrder} \leq \text{MaxFitOrder}</math>.</p>
Comment(s)	<ul style="list-style-type: none"> <li>–</li> </ul>		
Version info	<p>Available as of CalibrationLibrary DLL V1.0.0.</p> <p>Changed in CalibrationLibrary DLL V1.4.0. <code>MaxFitOrder</code>.</p>		

Name of the structure	VersionInfo		
Description	This structure defines: <ul style="list-style-type: none"> <li>The 3 number blocks of the currently running CalibrationLibrary DLL-Version ("Version n.n.n")</li> </ul>		
Used by	This structure is used with: <ul style="list-style-type: none"> <li><b>slcl_get_lib_version</b></li> </ul>		
Syntax	<pre>struct VersionInfo {     uint32_t Major;     uint32_t Minor;     uint32_t Revision; };</pre>		
Argument(s)	uint32_t	Major	Major-Version der CalibrationLibrary DLL.
	uint32_t	Minor	Minor-Version der CalibrationLibrary DLL.
	uint32_t	Revision	Revision der CalibrationLibrary DLL.
Comment(s)	<ul style="list-style-type: none"> <li>–</li> </ul>		
Version info	Available as of CalibrationLibrary DLL V1.0.0.		

## 5 Enumerated Types enum

In this chapter:

- enum `slcl_error_codes`
- enum `slcl_xy_calibration_options`

Name of the enum	slcl_error_codes
Description	<p>This enum defines the choices for:</p> <ul style="list-style-type: none"> <li>Standard return values of CalibrationLibrary functions</li> </ul>
Used by	<p>This enum is used with:</p> <ul style="list-style-type: none"> <li>All CalibrationLibrary-functions except <b>slcl_get_lib_version</b>.</li> </ul>
Syntax	<pre>enum slcl_error_codes {     NO_ERROR = 0,     ACTIVATION_CODE_INVALID = 1,     LIB_ACCESS_DENIED = 2,     WRONG_FILE_EXTENSION = 3,     COULD_NOT_OPEN_CORR_FILE = 4,     WRONG_FILE_SIZE = 5,     CHECKSUM_INVALID = 6,     BAD_HANDLE = 7,     WRONG_TABLETYPE = 8,     TABLE_NOT_3D = 9,     CALCULATION_FAILED = 10,     MISSING_README_PARAMS = 11,     INSUFFICIENT_MEMORY = 12,     INTERPOLATION_FAILED = 13,     SPLINE_INVERSION_FAILED = 14,     BAD_DIRECTION_VECTOR = 15,     RADIUS_TOO_SMALL = 16,     FUNCTION_CALL_NOT_ALLOWED = 17,     ANGLE_OUT_OF_BOUNDS = 18 };</pre>
Enumeration constant(s)	<div>NO_ERROR</div> <div>Call successful.</div>
	<div>ACTIVATION_CODE_INVALID</div> <div><b>slcl_activate</b> was called with the wrong password.</div>
	<div>LIB_ACCESS_DENIED</div> <div><b>slcl_activate</b> was never successfully called, access denied.</div>
	<div>WRONG_FILE_EXTENSION</div> <div>Submitted file name has neither ".ctb" nor ".ct5" extension.</div>
	<div>COULD_NOT_OPEN_CORR_FILE</div> <div><b>Correction file</b> could not be opened, possibly because it does not exist.</div>
	<div>WRONG_FILE_SIZE</div> <div>Specified file does not have the correct size.</div>
	<div>CHECKSUM_INVALID</div> <div>Specified file does not have a valid checksum.</div>
	<div>BAD_HANDLE</div> <div>The provided <b>Handle</b> is zero.</div>

Name of the enum	slcl_error_codes	
Enumeration constant(s) (cont'd)	WRONG_TABLETYPE	The provided <b>Handle</b> is Ct5 when Ct5 was expected or vice versa.
	TABLE_NOT_3D	The provided <b>Handle</b> is a <b>2D-Correction table</b> but must be a <b>3D-Correction table</b> .
	CALCULATION_FAILED	Calculation failed for miscellaneous reasons.
	MISSING_README_PARAMS	Parameters from the <b>Readme file</b> are missing, likely because a wrong path was provided during initialization.
	INSUFFICIENT_MEMORY	Not enough memory for calculation.
	INTERPOLATION_FAILED	<b>XY Calibration</b> interpolation failed.
	SPLINE_INVERSION_FAILED	<b>XY Calibration</b> spline inversion failed.
	BAD_DIRECTION_VECTOR	Direction vectors are either not perpendicular, or one has no x- and y-component.
	RADIUS_TOO_SMALL	Radius provided for <b>Cylinder Calibration</b> or <b>Cone Calibration</b> is not positive.
	FUNCTION_CALL_NOT_ALLOWED	The provided password does not authorize the use of this function.
	ANGLE_OUT_OF_BOUNDS	The specified <b>ConeInclinationAngleRad</b> value (of <b>slcl_do_cone_calibration</b> ) is either zero or not between $\pm\pi/3$ .
Version info	Available as of CalibrationLibrary DLL V1.0.0.	

Name of the enum	slcl_xy_calibration_options	
Description	This enum defines the choices for: <ul style="list-style-type: none"> <li>Boolean options for <b>XY Calibration</b> to be used in a bit field</li> </ul>	
Used by	This enum is used with: <ul style="list-style-type: none"> <li>struct <b>slcl_xy_calibration_settings</b></li> </ul>	
Syntax	<pre>enum slcl_xy_calibration_options {     RESTRICT_CORRECTION_FILE = 0x0001,     USE_POLYGON_RESTRICTION = 0x0002,     DO_AUTOMATIC_CALIBRATION_TO_RESTRICTION = 0x0004,     SET_CENTER_OFFSET_TO_ZERO = 0x0008,     USE_IMPROVE_OLD_FILE_MODE = 0x0010,     SET_MANUAL_CALIBRATION = 0x0020,     USE_AUTO_TOLERANCE = 0x0040,     FASTER_RUNTIME_FIND_FIT_ORDER = 0x0080,     USE_MAX_FIT_ORDER = 0x0100, };</pre>	
Enumeration constant(s)	RESTRICT_CORRECTION_FILE	If set: Resulting <b>Correction file</b> will be restricted to a certain area given by the measured points.
	USE_POLYGON_RESTRICTION	If set: Restricted area will be a convex polygon around measured points, otherwise a rectangle. Irrelevant if RESTRICT_CORRECTION_FILE is not set.
	DO_AUTOMATIC_CALIBRATION_TO_RESTRICTION	If set: Calibration Factor is automatically set so that the maximum bit control value corresponds to the edge of the restricted area. Irrelevant if RESTRICT_CORRECTION_FILE is not set.
	SET_CENTER_OFFSET_TO_ZERO	If set: Values at x=0, y=0 are unchanged for all calculated tables.
	USE_IMPROVE_OLD_FILE_MODE	If set: New table is calculated by improving the old table, otherwise table is calculated from scratch.
	SET_MANUAL_CALIBRATION	If set: Calibration factor is set to value provided under <b>NewCalibrationFactor</b> , otherwise the previous calibration factor is used. Important: This is overridden if DO_AUTOMATIC_CALIBRATION_TO_RESTRICTION and RESTRICT_CORRECTION_FILE are set to true!
	USE_AUTO_TOLERANCE	≥ V1.1: Deprecated. The optimal fit order is now always determined automatically. ≤ V1.0: If set: <b>XY Calibration</b> will automatically determine the quality of the measurements and adjust the fit tolerance accordingly.



Name of the enum	slcl_xy_calibration_options	
Enumeration constant(s) (cont'd)	FASTER_RUNTIME_FIND_FIT_ORDER	≥ V1.4.0. If set: A different algorithm is used to determine the optimal fit order. It is faster, but the calibration result may be less accurate. Therefore, set this bit only if the calculation time of the calibration step has a higher priority than the accuracy of the calibration.
	USE_MAX_FIT_ORDER	≥ V1.4.0. If set: <code>MaxFitOrder</code> from struct <b>slcl_xy_calibration_settings</b> , Page 58 is applied.
Version info	<p>Available as of CalibrationLibrary DLL V1.0.0.</p> <p>Changed in CalibrationLibrary DLL V1.1.0. <code>USE_AUTO_TOLERANCE</code>.</p> <p>Changed in CalibrationLibrary DLL V1.4.0. <code>FASTER_RUNTIME_FIND_FIT_ORDER</code>. <code>USE_MAX_FIT_ORDER</code>.</p>	



## 6 Example.cpp

```
#include "CalibrationLibrary.h"

#define RETURN_IF_ERROR(Expression) {uint32_t ErrorCode = (Expression); if (ErrorCode != 0) { return ErrorCode; } }
// Simple RAII wrapper for the CalibrationLibrary Handle.
class CalibrationLibraryHandler
{
public:
    // Construct providing the path of the correction file.
    CalibrationLibraryHandler(const char* CorrFilePath)
    {
        LoadError = slcl_load_correction_table(&CalibrationLibraryHandle, CorrFilePath, nullptr);
    }

    CalibrationLibraryHandler(const CalibrationLibraryHandler&) = delete;
    CalibrationLibraryHandler& operator=(const CalibrationLibraryHandler&) = delete;

    CalibrationLibraryHandler(CalibrationLibraryHandler&& In) noexcept
        : CalibrationLibraryHandle(In.CalibrationLibraryHandle)
        , LoadError(In.LoadError)
    {
        In.CalibrationLibraryHandle = 0;
        In.LoadError = 0;
    }
    CalibrationLibraryHandler& operator=(CalibrationLibraryHandler&& In) noexcept
    {
        if (&In != this)
        {
            CalibrationLibraryHandle = In.CalibrationLibraryHandle;
            LoadError = In.LoadError;
            In.CalibrationLibraryHandle = 0;
            In.LoadError = 0;
        }
        return *this;
    }

    // Automatically clean up the handle if it was successfully constructed previously.
    ~CalibrationLibraryHandler()
    {
        if (CalibrationLibraryHandle != 0)
        {
            slcl_delete_correction_table_handle(CalibrationLibraryHandle);
        }
    }
    // Returns the error code that was returned while loading the correction file.
    // Check this immediately after construction and abort if != 0.
    uint32_t getLoadErrorCode() const
    {
        return LoadError;
    }
    // Returns the successfully constructed Handle.
    size_t get() const
    {
        return CalibrationLibraryHandle;
    }
}
```



```
private:
    size_t CalibrationLibraryHandle = 0;
    uint32_t LoadError = 0;
};

uint32_t invTransform2dExample()
{
    const uint64_t ActivationCode = 0x0123456789ABCDEFU;
    // Replace with the correct activation code..
    const char* Filename = "Folder\\D3_9999.ct5";
    // Replace with the correct foldername and the correct filename.

    RETURN_IF_ERROR(slcl_activate(ActivationCode));
    // First activate the DLL with the correct password.

    CalibrationLibraryHandler MyHandler(Filename);
    RETURN_IF_ERROR(MyHandler.getLoadErrorCode());

    // points that are to be transformed
    const uint32_t NumberOfPoints = 5U;
    int32_t GalvoBitX[NumberOfPoints] = { -500000, -250000, 0, 250000, 500000 };
    // 20-bit values are used for all coordinates.
    int32_t GalvoBitY[NumberOfPoints] = { -400000, -100000, 0, 100000, 400000 };

    // Transform the points - in this case the input arrays will be overwritten with the results.
    return slcl_inverse_transform_points_2d_io(MyHandler.get(), NumberOfPoints, GalvoBitX, GalvoBitY);
}

uint32_t beamTiltCalibrationExample()
{
    const uint64_t ActivationCode = 0x0123456789ABCDEFU;
    // Replace with the correct activation code.
    const char* OriginalFilename = "Folder\\D3_9999.ct5";
    // Replace with the correct foldername and the correct filename.
    const char* CorrectedFilename = "Folder\\D3_9999_BeamTiltCalibration.ct5";
    // Replace with the desired foldername and filename.

    RETURN_IF_ERROR(slcl_activate(ActivationCode));
    // First activate the DLL with the correct password.

    CalibrationLibraryHandler MyHandler(OriginalFilename);
    RETURN_IF_ERROR(MyHandler.getLoadErrorCode());
    // Make sure that "D3_9999_ct5_ReadMe.txt" lies in the same folder as the correction file,
    // and if it does not, provide the readme path instead of "nullptr"!

    const double MeasuredOffsetXMM = 3.0;
    // Provide the measured offset from zero-position with galvo angles at zero in mm.
    const double MeasuredOffsetYMM = 2.0;

    return slcl_do_beam_tilt_calibration(MyHandler.get(), MeasuredOffsetXMM, MeasuredOffsetYMM, CorrectedFilename);
    // call beam tilt calibration
}
```



```
uint32_t xyCalibrationExample()
{
    const uint64_t ActivationCode = 0x0123456789ABCDEFU;
    // Replace with the correct activation code.
    const char* OriginalFilename = "Folder\\D3_9999_BeamTiltCalibration.ct5";
    // Replace with the correct foldername and the correct filename.
    const char* CorrectedFilename = "Folder\\D3_9999_XYCalibration.ct5";
    // Replace with the desired foldername and filename.

    RETURN_IF_ERROR(slcl_activate(ActivationCode));
    // First activate the DLL with the correct password.

    CalibrationLibraryHandler MyHandler(OriginalFilename);
    RETURN_IF_ERROR(MyHandler.getLoadErrorCode());

    const uint16_t NumberOfPoints = 25U;
    // For this example we'll go with 25 (5x5) measured points, but recommended is >=121 (11x11).

    // Provide the target bits.
    // It is also possible to provide the target positions in mm as double values.
    const int32_t XTargetsBit [NumberOfPoints] =
    {
        -500000, -250000, 0, 250000, 500000,
        -500000, -250000, 0, 250000, 500000,
        -500000, -250000, 0, 250000, 500000,
        -500000, -250000, 0, 250000, 500000,
        -500000, -250000, 0, 250000, 500000,
    };
    const int32_t YTargetsBit[NumberOfPoints] =
    {
        -500000, -500000, -500000, -500000, -500000,
        -250000, -250000, -250000, -250000, -250000,
        0, 0, 0, 0, 0,
        250000, 250000, 250000, 250000, 250000,
        500000, 500000, 500000, 500000, 500000,
    };

    // Then also provide the measured positions in mm.
    const double XMeasuredPositionsMM[NumberOfPoints] =
    {
        -177.56, -88.78, 0, 88.78, 177.56,
        -177.56, -88.78, 0, 88.78, 177.56,
        -177.56, -88.78, 0, 88.78, 177.56,
        -177.56, -88.78, 0, 88.78, 177.56,
        -177.56, -88.78, 0, 88.78, 177.56,
    };
    const double YMeasuredPositionsMM[NumberOfPoints] =
    {
        -177.56, -177.56, -177.56, -177.56, -177.56,
        -88.78, -88.78, -88.78, -88.78, -88.78,
        0, 0, 0, 0, 0,
        88.78, 88.78, 88.78, 88.78, 88.78,
        177.56, 177.56, 177.56, 177.56, 177.56,
    };
};
```



```
// Set other parameters for xy calibration.
slcl_xy_calibration_settings Params;
Params.XYCalibrationOptions = SET_CENTER_OFFSET_TO_ZERO | USE_IMPROVE_OLD_FILE_MODE;
Params.NewCalibrationFactor = 0;
Params.RestrictionScaling = 0.0;
Params.ToleranceUM = 20.0;

// Provide a struct to write the additional results into.
slcl_xy_calibration_interpolation_results Results;

// Call XY Calibration.
// If targets were provided in mm, call slcl_xy_calibration_mm_targets instead!
return slcl_xy_calibration_bit_targets(MyHandler.get(),
    NumberOfPoints,
    XTargetsBit,
    YTargetsBit,
    XMeasuredPositionsMM,
    YMeasuredPositionsMM,
    &Params,
    &Results,
    CorrectedFilename);
}

uint32_t abcCalibrationExample()
{
    const uint64_t ActivationCode = 0x0123456789ABCDEFU;
    // Replace with the correct activation code.
    const char* OriginalFilename = "Folder\\D3_9999_XYCalibration.ct5";
    // Replace with the correct foldername and the correct filename.
    const char* CorrectedFilename = "Folder\\D3_9999_ABCCalibration.ct5";
    // Replace with the desired foldername and filename.

    RETURN_IF_ERROR(slcl_activate(ActivationCode));
    // First activate the DLL with the correct password.

    CalibrationLibraryHandler MyHandler(OriginalFilename);
    RETURN_IF_ERROR(MyHandler.getLoadErrorCode());

    const uint16_t NMeasuredPoints = 7U;

    // Provide the measured focal lengths...
    const int32_t FocalLengthMeasurements[NMeasuredPoints] = { -160000, -8000, 0, 8000, 16000, 80000, 160000 };

    // ...and the measured z-output values.
    const int32_t ZOutputMeasurements[NMeasuredPoints] = { -348800, -12880, 3200, 19120, 34880, 155200, 291200 };

    // Also a struct to output the calculated coefficients into.
    // The new coefficients are also saved in the handle, but for ease of access they are written into this
    // struct after the calculation as well.
    slcl_abc_pol_coefficients ABCCorrResults;

    // Call ABCCalibration.
    return slcl_do_abc_calibration(MyHandler.get(), NMeasuredPoints, FocalLengthMeasurements, ZOutputMeasurements,
        CorrectedFilename, &ABCCorrResults);
}
```



```
uint32_t cylinderCalibrationExample()
{
    const uint64_t ActivationCode = 0x0123456789ABCDEFU;
    // Replace with the correct activation code.
    const char* OriginalFilename = "Folder\\D3_9999.ct5";
    // Replace with the correct foldername and the correct filename.
    const char* CorrectedFilename = "Folder\\D3_9999_CylinderCalibration.ct5";
    // Replace with the desired foldername and filename.

    RETURN_IF_ERROR(slcl_activate(ActivationCode));
    // First activate the DLL with the correct password.

    CalibrationLibraryHandler MyHandler(OriginalFilename);
    RETURN_IF_ERROR(MyHandler.getLoadErrorCode());

    // Example: Fit correction file to coffee mug.

    const double CoffeeMugDiameter = 81.2;

    // The new coordinate origin shall not be shifted in x/y direction.
    // However, the mug is simply placed on the z=0 plane, meaning that the
    // z coordinate at the coordinate origin is equal to its diameter.
    const double RefPoint[3] = { 0.0, 0.0, CoffeeMugDiameter};
    // The cylinder is placed parallel to the x-axis.
    const double DirectionVector[3] = { 1.0, 0.0, 0.0 };
    const double RadiusCoffeeMug = CoffeeMugDiameter * 0.5;

    // Call Cylinder Calibration.
    return slcl_do_cylinder_calibration(MyHandler.get(), RefPoint, DirectionVector, RadiusCoffeeMug, CorrectedFilename);
}

uint32_t focusCorrExample()
{
    const uint64_t ActivationCode = 0x0123456789ABCDEFU;
    // Replace with the correct activation code - will be provided by SCANLAB GmbH
    const char* OriginalFilename = "Folder\\D3_9999_XYCalibration.ct5";
    // Replace with the correct foldername and the correct filename.
    const char* CorrectedFilename = "Folder\\D3_9999_FocusCalibration.ct5";
    // Replace with the desired foldername and filename.

    RETURN_IF_ERROR(slcl_activate(ActivationCode));
    // First activate the DLL with the correct password.

    CalibrationLibraryHandler MyHandler(OriginalFilename);
    RETURN_IF_ERROR(MyHandler.getLoadErrorCode());

    const uint16_t NumberOfPoints = 25U;
    // For this example we'll go with 25 (5x5) measured points. It may be recommendable to use more.

    // Provide the targeted xy-bits.
    // The coordinates must be given in respect to the coordinate system of the target plane.
    const int32_t XTargetedPositionsBit[NumberOfPoints] =
    {
        -500000, -250000, 0, 250000, 500000,
        -500000, -250000, 0, 250000, 500000,
        -500000, -250000, 0, 250000, 500000,
        -500000, -250000, 0, 250000, 500000,
        -500000, -250000, 0, 250000, 500000,
    };
};
```



```

const int32_t YTargetedPositionsBit[NumberOfPoints] =
{
    -500000, -500000, -500000, -500000, -500000,
    -250000, -250000, -250000, -250000, -250000,
    0, 0, 0, 0, 0,
    250000, 250000, 250000, 250000, 250000,
    500000, 500000, 500000, 500000, 500000,
};

// Then also provide the z-bit values that gave the best spot size:
// To determine the optimal z-bit values use the RTC-command load_z_table followed by a select_cor_table command.
int32_t MeasuredOptimalZBits[NumberOfPoints] =
{
    282843, 223607, 200000, 223607, 282843,
    223607, 141421, 100000, 141421, 223607,
    200000, 100000, 0, 100000, 200000,
    223607, 141421, 100000, 141421, 223607,
    282843, 223607, 200000, 223607, 282843,
};

// The suggested RTC command procedure to find the values in the array above looks like this:
// ...
// load_correction_file(OriginalFilename, 1, 3); //load the correction file
// ...
// For all grid points X = XTargetedPositionsBit[i], Y = XTargetedPositionsBit[i] :
// load_z_table(MeasuredOptimalZBits[i], 0, 0); // changes A value in the ABC correction and therefore the focus position offset
// select_cor_table(1, 0); // applies the new A value
// repeat get_status(Busy, Pos) until Busy = 0; // wait for the select_cor_table done
// goto_xyz(X, Y, 0); //moves spot to the targeted X and Y position at Z=0(!) with modified Z offset
// // repeat the above while varying MeasuredOptimalZBits[i] until focal position is OK at the grid point X and Y
//

// Call Focus Calibration.
return slcl_do_focus_calibration(MyHandler.get(),
    NumberOfPoints,
    XTargetedPositionsBit,
    YTargetedPositionsBit,
    MeasuredOptimalZBits,
    CorrectedFilename);
}

```



## 7 Change Index

The following are changes in this manual due to the technical evolution of the product as well as significant editorial changes.

In this Chapter:

- [Changes to Document Revision 0.9.0 en-US from Document Revision 0.0.0 en-US](#)
- [Changes to Document Revision 1.0.0 en-US from Document Revision 0.9.0 en-US](#)
- [Changes to Document Revision 1.1.0 en-US from Document Revision 1.0.0 en-US](#)
- [Changes to Document Revision 1.2.0 en-US from Document Revision 1.1.0 en-US](#)

Changes to Document Revision **0.9.0 en-US** from Document Revision 0.0.0 en-US

Where (cont'd.)	What (cont'd.)
Global	Document Revision <ul style="list-style-type: none"><li>• 0.9.0 en-US</li></ul> applies to Calibration Library software package <ul style="list-style-type: none"><li>• V1.0.0</li></ul>
Global	First published version.
<a href="#">Change Index, page 72</a>	



## Changes to Document Revision 1.0.0 en-US from Document Revision 0.9.0 en-US

Where	What
Global	Document Revision <ul style="list-style-type: none"> <li>1.0.0 en-US</li> </ul> applies to Calibration Library software package <sup>(a)</sup> <ul style="list-style-type: none"> <li>V1.1.0</li> </ul>
<a href="#">slcl_inverse_transform_points_3d_io_with_trafos, Page 38</a>	Software change. New function.
<a href="#">slcl_inverse_transform_points_3d_with_trafos, Page 39</a>	Software change. New function.
<a href="#">slcl_additional_transformations, Page 52</a>	Software change. New struct.
<a href="#">slcl_xy_calibration_options, Page 64</a>	Software change. Changed enum <a href="#">slcl_xy_calibration_options</a> . Enumeration constant <code>USE_AUTO_TOLERANCE</code> <b>≥ V1.1: Deprecated</b> . The optimal fit order is now always determined automatically.
Change Index, page 72	

(a) #148051

## Changes to Document Revision 1.1.0 en-US from Document Revision 1.0.0 en-US

Where	What
Global	Document Revision <ul style="list-style-type: none"> <li>1.1.0 en-US</li> </ul> applies to Calibration Library software package <a href="#">#148051</a> <ul style="list-style-type: none"> <li>V1.2.0</li> </ul>
Change Index, page 72	

## Changes to Document Revision 1.2.0 en-US from Document Revision 1.1.0 en-US

Where	What
Global	Document Revision <ul style="list-style-type: none"> <li>1.2.0 en-US</li> </ul> applies to Calibration Library software package #148051 <ul style="list-style-type: none"> <li>V1.4.0</li> </ul>
struct <code>slcl_do_beam_tilt_calibration_measurement_data</code> , Page 20	See <a href="#">Version info</a> , page 20.
struct <code>slcl_xy_calibration_interpolation_results</code> , Page 56	Editorial change. Correction: <ul style="list-style-type: none"> <li><code>MaxPolyOrder</code> is of data type <code>uint32_t</code> (not: <code>int32_t</code>)</li> <li><code>GalvoLimitsReached</code> is of data type <code>uint32_t</code> (not: <code>int32_t</code>)</li> </ul>
struct <code>slcl_xy_calibration_settings</code> , Page 58	Editorial change. Correction: <ul style="list-style-type: none"> <li><code>XYCalibrationOptions</code> is of data type <code>uint32_t</code> (not: <code>int32_t</code>)</li> <li><code>NewCalibrationFactor</code> is of data type <code>uint32_t</code> (not: <code>int32_t</code>)</li> </ul>
struct <code>slcl_xy_calibration_settings</code> , Page 58	Software change. See <a href="#">Version info</a> , page 59.
enum <code>slcl_xy_calibration_options</code> , Page 64	Software change. See <a href="#">Version info</a> , page 65.
Change Index, page 72	